

PERFORCE

APIs for Scripting

2015.1

April 2015

APIs for Scripting

2015.1

April 2015

Copyright © 2008-2015 Perforce Software.

All rights reserved.

Perforce software and documentation is available from <http://www.perforce.com/>. You can download and use Perforce programs, but you can not sell or redistribute them. You can download, print, copy, edit, and redistribute the documentation, but you can not sell it, or sell any documentation derived from it. You can not modify or attempt to reverse engineer the programs.

This product is subject to U.S. export control laws and regulations including, but not limited to, the U.S. Export Administration Regulations, the International Traffic in Arms Regulation requirements, and all applicable end-use, end-user and destination restrictions. Licensee shall not permit, directly or indirectly, use of any Perforce technology in or by any U.S. embargoed country or otherwise in violation of any U.S. export control laws and regulations.

Perforce programs and documents are available from our Web site as is. No warranty or support is provided. Warranties and support, along with higher capacity servers, are sold by Perforce Software.

Perforce Software assumes no responsibility or liability for any errors or inaccuracies that might appear in this book. By downloading and using our programs and documents you agree to these terms.

Perforce and Inter-File Branching are trademarks of Perforce Software.

All other brands or product names are trademarks or registered trademarks of their respective companies or organizations.

Any additional software included within Perforce software is listed in [License Statements on page 171](#).

Table of Contents

Chapter 1	About This Manual	1
	Please give us feedback	1
Chapter 2	P4Ruby	3
	Introduction	3
	System Requirements	3
	Installing P4Ruby	3
	Programming with P4Ruby	4
	Connecting to SSL-enabled servers	4
	P4Ruby classes	5
	P4	5
	P4Exception	9
	P4::DepotFile	9
	P4::Revision	9
	P4::Integration	10
	P4::Map	10
	P4::MergeData	11
	P4::Message	11
	P4::OutputHandler	11
	P4::Progress	12
	P4::Spec	12
	Class P4	13
	Description	13
	Class Methods	13
	P4.identify -> aString	13
	P4.new -> aP4	13
	Instance Methods	14
	p4.api_level= anInteger -> anInteger	14
	p4.api_level -> anInteger	14
	p4.at_exception_level(lev) { ... } -> self	14
	p4.charset= aString -> aString	15
	p4.charset -> aString	15
	p4.client= aString -> aString	15
	p4.client -> aString	15
	p4.connect -> aBool	15
	p4.connected? -> aBool	16
	p4.cwd= aString -> aString	16
	p4.cwd -> aString	16
	p4.delete_<spectype>([options], name) -> anArray	16
	p4.disconnect -> true	17
	p4.each_<spectype>(arguments) -> anArray	17
	p4.env -> string	18
	p4.errors -> anArray	18
	p4.exception_level= anInteger -> anInteger	18

p4.exception_level -> aNumber	18
p4.fetch_<spectype>([name]) -> aP4::Spec	19
p4.format_spec("<spectype>", aHash)-> aString	19
p4.format_<spectype> aHash -> aHash	19
p4.handler= aHandler -> aHandler	20
p4.handler -> aHandler	20
p4.host= aString -> aString	20
p4.host -> aString	20
p4.input= (aString aHash anArray) -> aString aHash anArray	20
p4.maxlocktime= anInteger -> anInteger	21
p4.maxlocktime -> anInteger	21
p4.maxresults= anInteger -> anInteger	21
p4.maxresults -> anInteger	22
p4.maxscanrows= anInteger -> anInteger	22
p4.maxscanrows -> anInteger	22
p4.messages -> aP4::Message	22
p4.p4config_file -> aString	23
p4.parse_<spectype>(aString) -> aP4::Spec	23
p4.parse_spec("<spectype>", aString) -> aP4::Spec	23
p4.password= aString -> aString	23
p4.password -> aString	24
p4.port= aString -> aString	24
p4.port -> aString	24
p4.prog= aString -> aString	24
p4.prog -> aString	24
p4.progress= aProgress -> aProgress	25
p4.progress -> aProgress	25
p4.run_<cmd>(arguments) -> anArray	25
p4.run(aCommand, arguments...) -> anArray	25
p4.run_filelog(fileSpec) -> anArray	26
p4.run_login(arg...) -> anArray	27
p4.run_password(oldpass, newpass) -> anArray	27
p4.run_resolve(args) [block] -> anArray	27
p4.run_submit([aHash], [arg...]) -> anArray	28
p4.run_tickets() -> anArray	29
p4.save_<spectype>(hashOrString, [options]) -> anArray	29
p4.server_case_sensitive? -> aBool	29
p4.server_level -> anInteger	29
p4.server_unicode? -> aBool	29
p4.set_env= (aString, aString) -> aBool	30
p4.streams= -> aBool	30
p4.streams? -> aBool	30
p4.tagged(aBool) { block }	30
p4.tagged= aBool -> aBool	30
p4.tagged? -> aBool	30
p4.ticketfile= aString -> aString	31
p4.ticketfile -> aString	31
p4.track= -> aBool	31
p4.track? -> aBool	31
p4.track_output -> anArray	31
p4.user= aString -> aString	32

p4.user -> aString	32
p4.version= aString -> aString	32
p4.version -> aString	32
p4.warnings -> anArray	32
Class P4Exception	33
Class Methods	33
Instance Methods	33
Class P4::DepotFile	34
Description	34
Class Methods	34
Instance Methods	34
df.depot_file -> aString	34
df.each_revision { rev block } -> revArray	34
df.revisions -> aArray	34
Class P4::Revision	35
Description	35
Class Methods	35
Instance Methods	35
rev.action -> aString	35
rev.change -> aNumber	35
rev.client -> aString	35
rev.depot_file -> aString	35
rev.desc -> aString	35
rev.digest -> aString	35
rev.each_integration { integ block } -> integArray	35
rev.filesize -> aNumber	35
rev.integrations -> integArray	36
rev.rev -> aNumber	36
rev.time -> aTime	36
rev.type -> aString	36
rev.user -> aString	36
Class P4::Integration	37
Description	37
Class Methods	37
Instance Methods	37
integ.how -> aString	37
integ.file -> aPath	37
integ.srev -> aNumber	37
integ.erev -> aNumber	37
Class P4::Map	38
Description	38
Class Methods	38
Map.new ([anArray]) -> aMap	38
Map.join (map1, map2) -> aMap	38
Instance Methods	38
map.clear -> true	38
map.count -> anInteger	38
map.empty? -> aBool	38
map.insert(aString, [aString]) -> aMap	39
map.translate (aString, [aBool])-> aString	39
map.includes? (aString) -> aBool	39

map.reverse -> aMap	39
map.lhs -> anArray	39
map.rhs -> anArray	39
map.to_a -> anArray	39
Class P4::MergeData	40
Description	40
Class Methods	40
Instance Methods	40
md.your_name() -> aString	40
md.their_name() -> aString	40
md.base_name() -> aString	40
md.your_path() -> aString	40
md.their_path() -> aString	41
md.base_path() -> aString	41
md.result_path() -> aString	41
md.merge_hint() -> aString	41
md.run_merge() -> aBool	42
Class P4::Message	43
Description	43
Class methods	43
Instance methods	43
message.severity() -> anInteger	43
message.generic() -> anInteger	43
message.msgid() -> anInteger	43
message.to_s() -> aString	43
message.inspect() -> aString	43
Class P4::OutputHandler	44
Description	44
Class Methods	44
new P4::MyHandler.new -> aP4::OutputHandler	44
Instance Methods	44
outputBinary -> int	44
outputInfo -> int	44
outputMessage -> int	44
outputStat -> int	44
outputText -> int	44
Class P4::Progress	45
Description	45
Class Methods	45
new P4::MyProgress.new -> aP4::Progress	45
Instance Methods	45
init -> int	45
description -> int	45
update -> int	45
total -> int	45
done -> int	45
Class P4::Spec	46
Description	46
Class Methods	46
new P4::Spec.new(anArray) -> aP4::Spec	46
Instance Methods	46

spec._<fieldname> -> aValue	46
spec._<fieldname>= aValue -> aValue	46
spec.permitted_fields -> anArray	46
Chapter 3 P4Perl	49
Introduction	49
System Requirements	49
Installing P4Perl	49
Programming with P4Perl	49
Connecting to Perforce over SSL	50
P4Perl Classes	50
P4	51
P4::DepotFile	54
P4::Revision	54
P4::Integration	55
P4::Map	55
P4::MergeData	56
P4::Message	57
P4::OutputHandler	57
P4::Progress	57
P4::Resolver	58
P4::Spec	58
Class P4	59
Description	59
Class methods	59
P4::new() -> P4	59
P4::Identify() -> string	59
P4::ClearHandler() -> undef	60
P4::Connect() -> bool	60
P4::Disconnect() -> undef	60
P4::ErrorCount() -> integer	60
P4::Errors() -> list	60
P4::Fetch<Spectype>([name]) -> hashref	60
P4::Format<Spectype>(hash) -> string	60
P4::FormatSpec(\$spectype, \$string) -> string	61
P4::GetApiLevel() -> integer	61
P4::GetCharset() -> string	61
P4::GetClient() -> string	61
P4::GetCwd() -> string	61
P4::GetEnv(\$var) -> string	61
P4::GetHandler() -> Handler	62
P4::GetHost() -> string	62
P4::GetMaxLockTime(\$value) -> integer	62
P4::GetMaxResults(\$value) -> integer	62
P4::GetMaxScanRows(\$value) -> integer	62
P4::GetPassword() -> string	62
P4::GetPort() -> string	62
P4::GetProg() -> string	62

P4::GetProgress() -> Progress	62
P4::GetTicketFile([\$string]) -> string	62
P4::GetUser() -> String	62
P4::GetVersion(\$string) -> string	62
P4::IsConnected() -> bool	63
P4::IsStreams() -> bool	63
P4::IsTagged() -> bool	63
P4::IsTrack() -> bool	63
P4::Iterate<Spectype>(arguments) -> object	63
P4::Messages() -> list	63
P4::P4ConfigFile() -> string	64
P4::Parse<Spectype>(\$string) -> hashref	64
P4::ParseSpec(\$spectype, \$string) -> hashref	64
P4::Run<Cmd>([\$arg...]) -> list arrayref	64
P4::Run("<cmd>", [\$arg...]) -> list arrayref	65
P4::RunFilelog([\$args ...], \$fileSpec ...) -> list arrayref	66
P4::RunLogin(...) -> list arrayref	66
P4::RunPassword(\$oldpass, \$newpass) -> list arrayref	66
P4::RunResolve([\$resolver], [\$args ...]) -> string	66
P4::RunSubmit(\$arg \$hashref, ...) -> list arrayref	67
P4::RunTickets() -> list	67
P4::Save<Spectype>() -> list arrayref	67
P4::ServerCaseSensitive() -> integer	67
P4::ServerLevel() -> integer	67
P4::ServerUnicode() -> integer	68
P4::SetApiLevel(\$integer) -> undef	68
P4::SetCharset(\$charset) -> undef	68
P4::SetClient(\$client) -> undef	68
P4::SetCwd(\$path) -> undef	68
P4::SetEnv(\$var, \$value) -> undef	68
P4::SetHandler(Handler) -> Handler	69
P4::SetHost(\$hostname) -> undef	69
P4::SetInput(\$string \$hashref \$arrayref) -> undef	69
P4::SetMaxLockTime(\$integer) -> undef	69
P4::SetMaxResults(\$integer) -> undef	69
P4::SetMaxScanRows(\$integer) -> undef	69
P4::SetPassword(\$password) -> undef	69
P4::SetPort(\$port) -> undef	69
P4::SetProg(\$program_name) -> undef	70
P4::SetProgress(Progress) -> Progress	70
P4::SetStreams(0 1) -> undef	70
P4::SetTicketFile([\$string]) -> string	70
P4::SetTrack(0 1) -> undef	70
P4::SetUser(\$username) -> undef	70
P4::SetVersion(\$version) -> undef	70
P4::Tagged(0 1 \$coderef) -> undef	70
P4::TrackOutput() -> list	71
P4::WarningCount() -> integer	71
P4::Warnings() -> list	71
Class P4::DepotFile	72
Description	72

Class Methods	72
Instance Methods	72
\$df->DepotFile() -> string	72
\$df->Revisions() -> array	72
Class P4::Revision	73
Description	73
Class Methods	73
\$rev->Integrations() -> array	73
Instance Methods	73
\$rev->Action() -> string	73
\$rev->Change() -> integer	73
\$rev->Client() -> string	73
\$rev->DepotFile() -> string	73
\$rev->Desc() -> string	73
\$rev->Digest() -> string	73
\$rev->FileSize() -> string	73
\$rev->Rev() -> integer	73
\$rev->Time() -> string	74
\$rev->Type() -> string	74
\$rev->User() -> string	74
Class P4::Integration	75
Description	75
Class Methods	75
Instance Methods	75
\$integ->How() -> string	75
\$integ->File() -> string	75
\$integ->SRev() -> integer	75
\$integ->ERev() -> integer	75
Class P4::Map	76
Description	76
Class Methods	76
\$map = new P4::Map([array]) -> aMap	76
\$map->Join(map1, map2) -> aMap	76
Instance Methods	76
\$map->Clear() -> undef	76
\$map->Count() -> integer	76
\$map->IsEmpty() -> bool	76
\$map->Insert(string ...) -> undef	77
\$map->Translate(string, [bool]) -> string	77
\$map->Includes(string) -> bool	77
\$map->Reverse() -> aMap	77
\$map->Lhs() -> array	77
\$map->Rhs() -> array	77
\$map->AsArray() -> array	77
Class P4::MergeData	78
Description	78
Class Methods	78
Instance Methods	78
\$md.YourName() -> string	78
\$md.TheirName() -> string	78
\$md.BaseName() -> string	78

\$md.YourPath() -> string	78
\$md.TheirPath() -> string	78
\$md.BasePath() -> string	78
\$md.ResultPath() -> string	78
\$md.MergeHint() -> string	78
\$md.RunMergeTool() -> integer	79
Class P4::Message	80
Description	80
Class methods	80
Instance methods	80
\$message.GetSeverity() -> int	80
\$message.GetGeneric() -> int	80
\$message.GetId() -> int	80
\$message.GetText() -> int	80
Class P4::OutputHandler	81
Description	81
Class Methods	81
Instance Methods	81
\$handler.OutputBinary() -> int	81
\$handler.OutputInfo() -> int	81
\$handler.OutputMessage() -> int	81
\$handler.OutputStat()-> int	81
\$handler.OutputText() -> int	81
Class P4::Progress	82
Description	82
Class Methods	82
Instance Methods	82
\$progress.Init() -> int	82
\$progress.Description(string, int) -> int	82
\$progress.Update() -> int	82
\$progress.Total()-> int	82
\$progress.Done() -> int	82
Class P4::Resolver	83
Description	83
Class Methods	83
Instance Methods	83
\$resolver.Resolve() -> string	83
Class P4::Spec	84
Description	84
Class Methods	84
\$spec = new P4::Spec(\$fieldMap) -> array	84
Instance Methods	84
\$spec->_<fieldname> -> string	84
\$spec->_<fieldname>(\$string)-> string	84
\$spec->PermittedFields() -> array	84
Chapter 4 P4Python	85
Introduction	85

System Requirements	85
Installing P4Python	85
Programming with P4Python	86
Submitting a Changelist	87
Logging into Perforce using ticket-based authentication	87
Connecting to Perforce over SSL	88
Changing your password	88
Timestamp conversion	88
Working with comments in specs	89
P4Python Classes	89
P4	90
P4.P4Exception	93
P4.DepotFile	93
P4.Revision	94
P4.Integration	94
P4.Map	94
P4.MergeData	95
P4.Message	96
P4.OutputHandler	96
P4.Progress	96
P4.Resolver	97
P4.Spec	97
Class P4	98
Description	98
Instance Attributes	98
p4.api_level -> int	98
p4.charset -> string	99
p4.client -> string	99
p4.cwd -> string	99
p4.disable_tmp_cleanup -> string	99
p4.encoding -> string	100
p4.errors -> list (read-only)	100
p4.exception_level -> int	100
p4.handler -> handler	101
p4.host -> string	101
p4.ignore_file -> string	101
p4.input -> string dict list	101
p4.iterate_<spectype>(arguments) -> P4.Spec	102
p4.maxlocktime -> int	102
p4.maxresults -> int	102
p4.maxscanrows -> int	102
p4.messages -> list (read-only)	103
p4.p4config_file -> string (read-only)	103
p4.password -> string	103
p4.port -> string	103
p4.prog -> string	103
p4.progress -> progress	104
p4.server_case_insensitive -> boolean	104
p4.server_level -> int (read-only)	104
p4.server_unicode -> boolean	104
p4.streams -> int	104

p4.tagged -> int	104
p4.ticket_file -> string	105
p4.track -> boolean	105
p4.track_output -> list (read-only)	105
p4.user -> string	105
p4.version -> string	105
p4.warnings -> list (read-only)	105
Class Methods	106
P4.P4()	106
P4.clone(arguments...)	106
P4.identify()	107
P4.init([arguments])	107
Instance Methods	108
p4.at_exception_level()	108
p4.connect()	108
p4.connected() -> boolean	108
p4.delete_<spectype>([options], name) -> list	109
p4.disconnect()	109
p4.env(var)	110
p4.fetch_<spectype>() -> P4.Spec	110
p4.format_spec("<spectype>", dict) -> string	110
p4.format_<spectype>(dict) -> string	110
p4.is_ignored("<path>") -> boolean	110
p4.parse_spec("<spectype>", string) -> P4.Spec	111
p4.parse_<spectype>(string) -> P4.Spec	111
p4.run("<cmd>", [arg, ...])	111
p4.run_<cmd>()	113
p4.run_filelog(<fileSpec>) -> list	113
p4.run_login(<arg>...) -> list	114
p4.run_password(oldpass, newpass) -> list	114
p4.run_resolve([<resolver>], [arg...]) -> list	114
p4.run_submit([hash], [arg...]) -> list	115
p4.run_tickets() -> list	115
p4.save_<spectype>()>	115
p4.set_env(var, value)	116
p4.temp_client("<prefix>", "<template>")	116
p4.while_tagged(boolean)	116
Class P4.P4Exception	118
Description	118
Class Attributes	118
Class Methods	118
Class P4.DepotFile	119
Description	119
Instance Attributes	119
df.depotFile -> string	119
df.revisions -> list	119
Class Methods	119
Instance Methods	119
Class P4.Revision	120
Description	120
Instance Attributes	120

rev.action -> string	120
rev.change -> int	120
rev.client -> string	120
rev.depotFile -> string	120
rev.desc -> string	120
rev.digest -> string	120
rev.fileSize -> string	120
rev.integrations -> list	120
rev.rev -> int	120
rev.time -> datetime	121
rev.type -> string	121
rev.user -> string	121
Class Methods	121
Instance Methods	121
Class P4.Integration	122
Description	122
Instance Attributes	122
integ.how -> string	122
integ.file -> string	122
integ.srev -> int	122
integ.erev -> int	122
Class Methods	122
Instance Methods	122
Class P4.Map	123
Description	123
Instance Attributes	123
Class Methods	123
P4.Map([list]) -> P4.Map	123
P4.Map.join (map1, map2) -> P4.Map	123
Instance Methods	123
map.clear()	123
map.count() -> int	123
map.is_empty() -> boolean	124
map.insert(string ...)	124
map.translate (string, [boolean]) -> string	124
map.includes(string) -> boolean	124
map.reverse() -> P4.Map	124
map.lhs() -> list	124
map.rhs() -> list	124
map.as_array() -> list	125
Class P4.MergeData	126
Description	126
Instance Attributes	126
md.your_name -> string	126
md.their_name -> string	126
md.base_name -> string	126
md.your_path -> string	126
md.their_path -> string	126
md.base_path -> string	126
md.result_path -> string	126
md.merge_hint -> string	126

Instance Methods	126
md.run_merge() -> boolean	126
Class P4.Message	127
Description	127
Class Methods	127
Instance Attributes	127
message.severity -> int	127
message.generic -> int	127
message.msgid -> int	127
Class P4.OutputHandler	128
Description	128
Class Methods	128
class MyHandler(P4.OutputHandler)	128
Instance Methods	128
outputBinary -> int	128
outputInfo -> int	128
outputMessage -> int	128
outputStat -> int	128
outputText -> int	128
Class P4.Progress	129
Description	129
Instance Attributes	129
Class Methods	129
class MyProgress(P4.Progress)	129
Instance Methods	129
progress.init() -> int	129
progress.setDescription(string, int) -> int	129
progress.update() -> int	129
progress.setTotal(<total>) -> int	129
progress.done() -> int	129
Class P4.Resolver	130
Description	130
Instance Attributes	130
Class Methods	130
Instance Methods	130
resolver.resolve(self, mergeData) -> string	130
Class P4.Spec	131
Description	131
Instance Attributes	131
spec._<fieldname> -> string	131
spec.comment -> dict	131
spec.permitted_fields -> dict	131
Class Methods	131
P4.Spec.new(dict) -> P4.Spec	131
Instance Methods	131
Chapter 5 P4PHP	133
Introduction	133

System Requirements	133
Installing P4PHP	133
Programming with P4PHP	133
Submitting a Changelist	134
Logging into Perforce using ticket-based authentication	135
Connecting to Perforce over SSL	135
Changing your password	135
P4PHP Classes	136
P4	136
P4_Exception	139
P4_DepotFile	139
P4_Revision	139
P4_Integration	140
P4_Map	140
P4_MergeData	141
P4_OutputHandlerAbstract	141
P4_Resolver	142
Class P4	143
Description	143
Properties	143
P4::api_level -> int	143
P4::charset -> string	144
P4::client -> string	144
P4::cwd -> string	144
P4::errors -> array (read-only)	145
P4::exception_level -> int	145
P4::expand_sequences -> bool	145
P4::handler -> handler	146
P4::host -> string	146
P4::input -> string array	146
P4::maxlocktime -> int	147
P4::maxresults -> int	147
P4::maxscanrows -> int	147
P4::p4config_file -> string (read-only)	147
P4::password -> string	147
P4::port -> string	148
P4::prog -> string	148
P4::server_level -> int (read-only)	149
P4::streams -> bool	149
P4::tagged -> bool	149
P4::ticket_file -> string	149
P4::user -> string	149
P4::version -> string	150
P4::warnings -> array (read-only)	150
Constructor	150
P4::__construct	150
Static Methods	151
P4::identify() -> string	151
Instance Methods	151
P4::connect() -> bool	151
P4::connected() -> bool	151

P4::delete_<spectype>([options], name) -> array	152
P4::disconnect() -> void	152
P4::env(var) -> string	153
P4::fetch_<spectype>() -> array	153
P4::format_spec("<spectype>", array) -> string	153
P4::format_<spectype>(array) -> string	154
P4::parse_spec("<spectype>", string) -> array	154
P4::parse_<spectype>(string) -> array	154
P4::run(<cmd>, [arg, ...]) -> mixed	154
P4::run_<cmd>() -> mixed	156
P4::run_filelog(<fileSpec>) -> array	157
P4::run_login(arg...) -> array	157
P4::run_password(oldpass, newpass) -> array	157
P4::run_resolve([<resolver>], [arg...]) -> array	158
P4::run_submit([array], [arg...]) -> array	159
P4::save_<spectype>()>	159
Class P4_Exception	160
Description	160
Class Attributes	160
Static Methods	160
Class P4_DepotFile	161
Description	161
Properties	161
\$df->depotFile -> string	161
\$df->revisions -> array	161
Static Methods	161
Instance Methods	161
Class P4_Revision	162
Description	162
Properties	162
\$rev->action -> string	162
\$rev->change -> long	162
\$rev->client -> string	162
\$rev->depotFile -> string	162
\$rev->desc -> string	162
\$rev->digest -> string	162
\$rev->fileSize -> long	162
\$rev->integrations -> array	162
\$rev->rev -> long	162
\$rev->time -> string	163
\$rev->type -> string	163
\$rev->user -> string	163
Static Methods	163
Instance Methods	163
Class P4_Integration	164
Description	164
Properties	164
\$integ->how -> string	164
\$integ->file -> string	164
\$integ->srev -> int	164
\$integ->erev -> int	164

Static Methods	164
Instance Methods	164
Class P4_Map	165
Description	165
Properties	165
Constructor	165
P4_Map::__construct([array]) -> P4_Map	165
Static Methods	165
P4_Map::join (map1, map2) -> P4_Map	165
Instance Methods	165
\$map->clear() -> void	165
\$map->count() -> int	165
\$map->is_empty() -> bool	166
\$map->insert(string ...) -> void	166
\$map->translate (string, [bool])-> string	166
\$map->includes(string) -> bool	166
\$map->reverse() -> P4_Map	166
\$map->lhs() -> array	166
\$map->rhs() -> array	166
\$map->as_array() -> array	167
Class P4_MergeData	168
Description	168
Properties	168
\$md->your_name -> string	168
\$md->their_name -> string	168
\$md->base_name -> string	168
\$md->your_path -> string	168
\$md->their_path -> string	168
\$md->base_path -> string	168
\$md->result_path -> string	168
\$md->merge_hint -> string	168
Class P4_OutputHandlerAbstract	169
Description	169
Class Methods	169
class MyHandler extends P4_OutputHandlerAbstract	169
Instance Methods	169
\$handler->outputBinary -> int	169
\$handler->outputInfo -> int	169
\$handler->outputMessage -> int	169
\$handler->outputStat -> int	169
\$handler->outputText -> int	169
Class P4_Resolver	170
Description	170
Properties	170
Static Methods	170
Instance Methods	170
\$resolver->resolve(self, mergeData) -> string	170

License Statements	171
--------------------------	-----

This guide contains details about using the derived APIs for Ruby, Perl, Python, and PHP to create scripts that interact correctly with the Perforce versioning service. You can download these APIs from the Perforce web site:

<http://www.perforce.com/product/components/apis>

These derived APIs depend on the C/C++ API. See the *Perforce C/C++ API User's Guide* for details.

Please give us feedback

If you have any feedback for us, or detect any errors in this guide, please email details to `<manual@perforce.com>`.

Introduction

P4Ruby is an extension to the Ruby programming language that allows you to run Perforce commands from within Ruby scripts, and get the results in a Ruby-friendly format.

The main features are:

- Get Perforce data and forms in hashes and arrays.
- Edit Perforce forms by modifying hashes.
- Exception based error handling.
- Controllable handling of warnings such as "File(s) up-to-date." on a sync.
- Run as many commands on a connection as required.
- The output of a command is returned as a Ruby array. For non-tagged output, the elements of the array are strings. For tagged output, the elements of the array are Ruby hashes. For forms, the output is an array of **P4::Spec** objects.
- Thread-safe and thread-friendly; you can have multiple instances of the **P4** class running in different threads.
- Exception-based error handling. Trap **P4Exceptions** for complete, high-level error handling.

The most recent release of P4Ruby is 2014.1.

System Requirements

P4Ruby is supported on Windows, Linux, Solaris, OS X, and FreeBSD.

To build P4Ruby, your development machine must also have:

- Ruby 1.8 or 1.9 development files.
- **make** (or **nmake** on Windows).
- The 2014.1 Perforce C/C++ API for your target platform. Older releases might work, but are not supported.
- The same C++ compiler used to build the Perforce C++ API on your target platform.

(If you get "unresolved symbol" errors when building or running P4Ruby, you probably used the wrong compiler or the wrong Perforce API build.)

Installing P4Ruby

As of version 2015.1, the recommended mechanism for installing P4Ruby is via gems.

Outside of Windows, the **p4ruby** gem installs must be compiled locally against your installation of Ruby. If you can build the core Ruby distribution locally, you likely can install P4Ruby without incident. On Windows, precompiled gems will be made available.

```
$ gem install p4ruby -- --with-p4api-dir=DIR
```

In the example above, the *DIR* is the path to a local copy of the Perforce C++ API distribution. The Perforce C++ API should match the major and minor version of P4Ruby. If you omit the `--with-p4api-dir` option, the gem attempts to download a version of the API itself from ftp.perforce.com.

More installation options are described in the P4Ruby project in the Perforce Workshop:

<https://swarm.workshop.perforce.com/projects/perforce-software-p4ruby>

Programming with P4Ruby

The following example shows how to create a new client workspace based on an existing template:

```
require "P4"
template = "my-client-template"
client_root = 'c:\p4-work'
p4 = P4.new
p4.connect

begin

  # Run a "p4 client -t template -o" and convert it into a Ruby hash
  spec = p4.fetch_client( "-t", template, "my-new-client")

  # Now edit the fields in the form
  spec[ "Root" ] = client_root
  spec[ "Options" ] = spec[ "Options" ].sub( "normdir", "rmdir" )

  # Now save the updated spec
  p4.save_client( spec )

  # Point to the newly-created client
  p4.client="my-new-client"

  # And sync it.
  p4.run_sync

rescue P4Exception
  # If any errors occur, we'll jump in here. Just log them
  # and raise the exception up to the higher level

  p4.errors.each { |e| $stderr.puts( e ) }
  raise
end
```

Connecting to SSL-enabled servers

Scripts written with P4Ruby use any existing **P4TRUST** file present in their operating environment (by default, `.p4trust` in the home directory of the user that runs the script).

If the fingerprint returned by the server fails to match the one installed in the **P4TRUST** file associated with the script's run-time environment, your script will (and should!) fail to connect to the server.

P4Ruby classes

The P4 module consists of several public classes:

- [“P4” on page 5](#)
- [“P4Exception” on page 9](#)
- [“P4::DepotFile” on page 9](#)
- [“P4::Revision” on page 9](#)
- [“P4::Integration” on page 10](#)
- [“P4::Map” on page 10](#)
- [“P4::MergeData” on page 11](#)
- [“P4::Message” on page 11](#)
- [“P4::OutputHandler” on page 11](#)
- [“P4::Progress” on page 12](#)
- [“P4::Spec” on page 12](#)

The following tables provide brief details about each public class.

P4

The main class used for executing Perforce commands. Almost everything you do with P4Ruby will involve this class.

Method	Description
identify	Return the version of P4Ruby in use (class method).
new	Construct a new P4 object (class method).
api_level=	Set desired API compatibility level.
api_level	Return current API compatibility level.
at_exception_level	Execute the associated block under a specific exception level, returning to previous exception level when block returns.
charset=	Set character set when connecting to Unicode servers.
charset	Get character set when connecting to Unicode servers.
client=	Set client workspace (P4CLIENT).

Method	Description
<u>client</u>	Get current client workspace (P4CLIENT).
<u>connect</u>	Connect to the Perforce Server, raise P4Exception on failure.
<u>connected?</u>	Test whether or not session has been connected and/or has been dropped.
<u>cwd=</u>	Set current working directory.
<u>cwd</u>	Get current working directory.
<u>delete_<spectype></u>	Shortcut methods for deleting clients, labels, etc.
<u>disconnect</u>	Disconnect from the Perforce Server.
<u>each_<spectype></u>	Shortcut methods for iterating through clients, labels, etc.
<u>env</u>	Get the value of a Perforce environment variable, taking into account P4CONFIG files and (on Windows or OS X) the registry or user preferences.
<u>errors</u>	Return the array of errors that occurred during execution of previous command.
<u>exception_level=</u>	Control which types of events give rise to exceptions (P4::RAISE_NONE , RAISE_ERRORS , or RAISE_ALL).
<u>exception_level</u>	Return the current exception level.
<u>fetch_<spectype></u>	Shortcut methods for retrieving the definitions of clients, labels, etc.
<u>format_spec</u>	Convert fields in a hash containing the elements of a Perforce form (spec) into the string representation familiar to users.
<u>format_<spectype></u>	Shortcut method; equivalent to: <pre>p4.format_spec("<spectype>", aHash)</pre>
<u>handler=</u>	Set output handler.
<u>handler</u>	Get output handler.
<u>host=</u>	Set the name of the current host (P4HOST).
<u>host</u>	Get the current hostname.
<u>input=</u>	Store input for next command.
<u>maxlocktime=</u>	Set MaxLockTime used for all following commands.

Method	Description
<u>maxlocktime</u>	Get MaxLockTime used for all following commands.
<u>maxresults=</u>	Set MaxResults used for all following commands.
<u>maxresults</u>	Get MaxResults used for all following commands.
<u>maxscanrows=</u>	Set MaxScanRows used for all following commands.
<u>maxscanrows</u>	Get MaxScanRows used for all following commands.
<u>messages</u>	Returns all messages from the server as P4::Message objects.
<u>p4config_file</u>	Get the location of the configuration file used (P4CONFIG).
<u>parse_<spectype></u>	Shortcut method; equivalent to: <pre>p4.parse_spec("<spectype>", aString)</pre>
<u>parse_spec</u>	Parses a Perforce form (spec) in text form into a Ruby hash using the spec definition obtained from the server.
<u>password=</u>	Set Perforce password (P4PASSWD).
<u>password</u>	Get the current password or ticket.
<u>port=</u>	Set host and port (P4PORT).
<u>port</u>	Get host and port (P4PORT) of the current Perforce server.
<u>prog=</u>	Set program name as shown by p4 monitor show -e .
<u>prog</u>	Get program name as shown by p4 monitor show -e .
<u>progress=</u>	Set progress indicator.
<u>progress</u>	Get progress indicator.
<u>run_cmd</u>	Shortcut method; equivalent to: <pre>p4.run("cmd", arguments...)</pre>
<u>run</u>	Runs the specified Perforce command with the arguments supplied.
<u>run_filelog</u>	Runs a p4 filelog on the fileSpec provided, returns an array of P4::DepotFile objects.
<u>run_login</u>	Runs p4 login using a password or ticket set by the user.

Method	Description
<u>run_password</u>	A thin wrapper to make it easy to change your password.
<u>run_resolve</u>	Interface to <code>p4 resolve</code> .
<u>run_submit</u>	Submit a changelist to the server.
<u>run_tickets</u>	Get a list of tickets from the local tickets file.
<u>save_<spectype></u>	Shortcut method; equivalent to: <pre>p4.input = hashOrString p4.run("<spectype>", "-i")</pre>
<u>server_case_sensitive?</u>	Detects whether or not the server is case sensitive.
<u>server_level</u>	Returns the current Perforce server level.
<u>server_unicode?</u>	Detects whether or not the server is in unicode mode.
<u>set_env</u>	On Windows or OS X, set a variable in the registry or user preferences.
<u>streams=</u>	Enable or disable support for streams.
<u>streams?</u>	Test whether or not the server supports streams
<u>tagged</u>	Toggles tagged output (true or false). By default, tagged output is on.
<u>tagged=</u>	Sets tagged output. By default, tagged output is on.
<u>tagged?</u>	Detects whether or not tagged output is enabled.
<u>ticketfile=</u>	Set the location of the <code>P4TICKETS</code> file.
<u>ticketfile</u>	Get the location of the <code>P4TICKETS</code> file.
<u>track=</u>	Activate or disable server performance tracking.
<u>track?</u>	Detect whether server performance tracking is active.
<u>track_output</u>	Returns server tracking output.
<u>user=</u>	Set the Perforce username (<code>P4USER</code>).
<u>user</u>	Get the Perforce username (<code>P4USER</code>).
<u>version=</u>	Set your script's version as reported to the server.
<u>version</u>	Get your script's version as reported by the server.

Method	Description
<code>warnings</code>	Returns the array of warnings that arose during execution of the last command.

P4Exception

Used as part of error reporting and is derived from the Ruby `RuntimeError` class.

P4::DepotFile

Utility class allowing access to the attributes of a file in the depot. Returned by `P4#run_filelog()`.

Method	Description
<code>depot_file</code>	Name of the depot file to which this object refers.
<code>each_revision</code>	Iterates over each revision of the depot file.
<code>revisions</code>	Returns an array of revision objects for the depot file.

P4::Revision

Utility class allowing access to the attributes of a revision `P4::DepotFile` object. Returned by `P4#run_filelog()`.

Method	Description
<code>action</code>	Action that created the revision.
<code>change</code>	Changelist number.
<code>client</code>	Client workspace used to create this revision.
<code>depot_file</code>	Name of the file in the depot.
<code>desc</code>	Short changelist description.
<code>digest</code>	MD5 digest of this revision.
<code>filesize</code>	Returns the size of this revision.
<code>integrations</code>	Array of <code>P4::Integration</code> objects.
<code>rev</code>	Revision number.
<code>time</code>	Timestamp.
<code>type</code>	Perforce file type.

Method	Description
user	User that created this revision.

P4::Integration

Utility class allowing access to the attributes of an integration record for a `P4::Revision` object. Returned by `P4#run_filelog()`.

Method	Description
how	Integration method (merge/branch/copy/ignored).
file	Integrated file.
srev	Start revision.
erev	End revision.

P4::Map

A class that allows users to create and work with Perforce mappings without requiring a connection to the Perforce Server.

Method	Description
new	Construct a new map object (class method).
join	Joins two maps to create a third (class method).
clear	Empties a map.
count	Returns the number of entries in a map.
empty?	Tests whether or not a map object is empty.
insert	Inserts an entry into the map.
translate	Translate a string through a map.
includes?	Tests whether a path is mapped.
reverse	Returns a new mapping with the left and right sides reversed.
lhs	Returns the left side as an array.
rhs	Returns the right side as an array.
to_a	Returns the map as an array.

P4::MergeData

Class encapsulating the context of an individual merge during execution of a `p4 resolve` command. Passed as a parameter to the block passed to `P4#run_resolve()`.

Method	Description
<code>your_name</code>	Returns the name of "your" file in the merge. (file in workspace)
<code>their_name</code>	Returns the name of "their" file in the merge. (file in the depot)
<code>base_name</code>	Returns the name of "base" file in the merge. (file in the depot)
<code>your_path</code>	Returns the path of "your" file in the merge. (file in workspace)
<code>their_path</code>	Returns the path of "their" file in the merge. (temporary file on workstation into which <code>their_name</code> has been loaded)
<code>base_path</code>	Returns the path of the base file in the merge. (temporary file on workstation into which <code>base_name</code> has been loaded)
<code>result_path</code>	Returns the path to the merge result. (temporary file on workstation into which the automatic merge performed by the server has been loaded)
<code>merge_hint</code>	Returns hint from server as to how user might best resolve merge.
<code>run_merge</code>	If the environment variable <code>P4MERGE</code> is defined, run it and return a boolean based on the return value of that program.

P4::Message

Utility class allowing access to the attributes of a message object returned by `P4#messages()`.

Method	Description
<code>severity</code>	Returns the severity of the message.
<code>generic</code>	Returns the generic class of the error.
<code>msgid</code>	Returns the unique ID of the error message.
<code>to_s</code>	Returns the error message as a string.
<code>inspect</code>	Converts the error object into a string for debugging purposes.

P4::OutputHandler

Handler class that provides access to streaming output from the server; set `P4#handler()` to an instance of a subclass of `P4::OutputHandler` to enable callbacks:

Method	Description
<code>outputBinary</code>	Process binary data.
<code>outputInfo</code>	Process tabular data.
<code>outputMessage</code>	Process information or errors.
<code>outputStat</code>	Process tagged output.
<code>outputText</code>	Process text data.

P4::Progress

Handler class that provides access to progress indicators from the server; set `P4#progress()` to an instance of a subclass of `P4::Progress` with the following methods (even if the implementations are empty) to enable callbacks:

Method	Description
<code>init</code>	Initialize progress indicator as designated type.
<code>total</code>	Total number of units (if known).
<code>description</code>	Description and type of units to be used for progress reporting.
<code>update</code>	If non-zero, user has requested a cancellation of the operation.
<code>done</code>	If non-zero, operation has failed.

P4::Spec

Subclass of hash allowing access to the fields in a Perforce specification form. Also checks that the fields that are set are valid fields for the given type of spec. Returned by `P4#fetch_<spectype>()`.

Method	Description
<code>spec._fieldname</code>	Return the value associated with the field named <i>fieldname</i> .
<code>spec._fieldname=</code>	Set the value associated with the field named <i>fieldname</i> .
<code>spec.permitted_fields</code>	Returns an array containing the names of fields that are valid in this spec object.

Class P4

Description

Main interface to the Perforce client API. Each **P4** object provides you with a thread-safe API level interface to Perforce. The basic model is to:

1. Instantiate your **P4** object.
2. Specify your Perforce client environment.
 - **client**
 - **host**
 - **password**
 - **port**
 - **user**
3. Set any options to control output or error handling:
 - **exception_level**
4. Connect to the Perforce service.

The Perforce protocol is not designed to support multiple concurrent queries over the same connection. Multithreaded applications that use the C++ API or derived APIs (including P4Ruby) should ensure that a separate connection is used for each thread, or that only one thread may use a shared connection at a time.

5. Run your Perforce commands.
6. Disconnect from the Perforce service.

Class Methods

P4.identify -> aString

Return the version of P4Ruby that you are using. Also reports the version of the OpenSSL library used for building the underlying Perforce C++ API with which P4Ruby was built.

```
ruby -rP4 -e 'puts( P4.identify )'
```

Some of this information is already made available through the predefined constants **P4::VERSION**, **P4::OS**, and **P4::PATCHLEVEL**.

P4.new -> aP4

Constructs a new P4 object.

```
p4 = P4.new()
```

Instance Methods

p4.api_level= anInteger -> anInteger

Sets the API compatibility level desired. This is useful when writing scripts using Perforce commands that do not yet support tagged output. In these cases, upgrading to a later server that supports tagged output for the commands in question can break your script. Using this method allows you to lock your script to the output format of an older Perforce release and facilitate seamless upgrades. This method *must* be called prior to calling **P4#connect()**.

```
p4 = P4.new
p4.api_level = 67 # Lock to 2010.1 format
p4.connect
...
```

For the API integer levels that correspond to each Perforce release, see:

<http://kb.perforce.com/article/512>

p4.api_level -> anInteger

Returns the current Perforce API compatibility level. Each iteration of the Perforce Server is given a level number. As part of the initial communication, the client protocol level is passed between client application and the Perforce Server. This value, defined in the Perforce API, determines the communication protocol level that the Perforce client will understand. All subsequent responses from the Perforce Server can be tailored to meet the requirements of that client protocol level.

For more information, see:

<http://kb.perforce.com/article/512>

p4.at_exception_level(lev) { ... } -> self

Executes the associated block under a specific exception level. Returns to the previous exception level when the block returns.

```
p4 = P4.new
p4.client = "www"
p4.connect

p4.at_exception_level( P4::RAISE_ERRORS ) do
  p4.run_sync
end

p4.disconnect
```

p4.charset= aString -> aString

Sets the character set to use when connect to a Unicode enabled server. Do not use when working with non-Unicode-enabled servers. By default, the character set is the value of the **P4CHARSET** environment variable. If the character set is invalid, this method raises a **P4Exception**.

```
p4 = P4.new
p4.client = "www"
p4.charset = "iso8859-1"
p4.connect
p4.run_sync
p4.disconnect
```

p4.charset -> aString

Get the name of the character set in use when working with Unicode-enabled servers.

```
p4 = P4.new
p4.charset = "utf8"
puts( p4.charset )
```

p4.client= aString -> aString

Set the name of the client workspace you wish to use. If not called, defaults to the value of **P4CLIENT** taken from any **P4CONFIG** file present, or from the environment as per the usual Perforce convention. Must be called before connecting to the Perforce server.

```
p4 = P4.new
p4.client = "www"
p4.connect
p4.run_sync
p4.disconnect
```

p4.client -> aString

Get the name of the Perforce client currently in use.

```
p4 = P4.new
puts( p4.client )
```

p4.connect -> aBool

Connect to the Perforce Server. You must connect before you can execute commands. Raises a **P4Exception** if the connection attempt fails.

```
p4 = P4.new  
p4.connect
```

p4.connected? -> aBool

Test whether or not the session has been connected, and if the connection has not been dropped.

```
p4 = P4.new  
p4.connected?
```

p4.cwd= aString -> aString

Sets the current working directory. Can be called prior to executing any Perforce command. Sometimes necessary if your script executes a `chdir()` as part of its processing.

```
p4 = P4.new  
p4.cwd = "/home/bruno"
```

p4.cwd -> aString

Get the current working directory.

```
p4 = P4.new  
puts( p4.cwd )
```

p4.delete_<spectype>([options], name) -> anArray

The delete methods are simply shortcut methods that allow you to quickly delete the definitions of clients, labels, branches, etc. These methods are equivalent to:

```
p4.run( "<spectype>", '-d', [options], "spec name" )
```

For example:

```

require "P4"
require "parsedate"
include ParseDate
now = Time.now
p4 = P4.new
begin
  p4.connect
  p4.run_clients.each do
    |client|
      atime = parsedate( client[ "Access" ] )
      if( (atime + 24 * 3600 * 365 ) < now )
        p4.delete_client( '-f', client[ "client" ] )
      end
    end
  end
rescue P4Exception
  p4.errors.each { |e| puts( e ) }
ensure
  p4.disconnect
end

```

p4.disconnect -> true

Disconnect from the Perforce Server.

```

p4 = P4.new
p4.connect
p4.disconnect

```

p4.each_<spectype>(arguments) -> anArray

The `each_<spectype>` methods are shortcut methods that allow you to quickly iterate through clients, labels, branches, etc. Valid *<spectype>*s are **clients**, **labels**, **branches**, **changes**, **streams**, **jobs**, **users**, **groups**, **depots** and **servers**. Valid arguments are any arguments that would be valid for the corresponding `run_<spectype>` command.

For example, to iterate through clients:

```

p4.each_clients do
  |c|
    # work with the retrieved client spec
end

```

is equivalent to:

```

clients = p4.run_clients
clients.each do
|c|
  client = p4.fetch_client( c['client'] )
  # work with the retrieved client spec
end

```

p4.env -> string

Get the value of a Perforce environment variable, taking into account **P4CONFIG** files and (on Windows and OS X) the registry or user preferences.

```

p4 = P4.new
puts p4.env( "P4PORT" )

```

p4.errors -> anArray

Returns the array of errors which occurred during execution of the previous command.

```

p4 = P4.new
begin
  p4.connect
  p4.exception_level( P4::RAISE_ERRORS ) # ignore "File(s) up-to-date"
  files = p4.run_sync
rescue P4Exception
  p4.errors.each { |e| puts( e ) }
ensure
  p4.disconnect
end

```

p4.exception_level= anInteger -> anInteger

Configures the events which give rise to exceptions. The following three levels are supported:

- **P4::RAISE_NONE** disables all exception raising and makes the interface completely procedural.
- **P4::RAISE_ERRORS** causes exceptions to be raised only when errors are encountered.
- **P4::RAISE_ALL** causes exceptions to be raised for both errors and warnings. This is the default.

```

p4 = P4.new
p4.exception_level = P4::RAISE_ERRORS
p4.connect # P4Exception on failure
p4.run_sync # File(s) up-to-date is a warning so no exception is raised
p4.disconnect

```

p4.exception_level -> aNumber

Returns the current exception level.

p4.fetch_<spectype>([name]) -> aP4::Spec

The `fetch_<spectype>` methods are shortcut methods that allow you to quickly fetch the definitions of clients, labels, branches, etc. They're equivalent to:

```
p4.run( "<spectype>", '-o', ... ).shift
```

For example:

```
p4 = P4.new
begin
  p4.connect
  client      = p4.fetch_client()
  other_client = p4.fetch_client( "other" )
  label       = p4.fetch_label( "somelabel" )
rescue P4Exception
  p4.errors.each { |e| puts( e ) }
ensure
  p4.disconnect
end
```

p4.format_spec("<spectype>", aHash) -> aString

Converts the fields in a hash containing the elements of a Perforce form (spec) into the string representation familiar to users.

The first argument is the type of spec to format: for example, `client`, `branch`, `label`, and so on. The second argument is the hash to parse.

There are shortcuts available for this method. You can use:

```
p4.format_<spectype>( hash )
```

instead of:

```
p4.format_spec( "<spectype>", hash )
```

where `<spectype>` is the name of a Perforce spec, such as `client`, `label`, etc.

p4.format_<spectype> aHash -> aHash

The `format_<spectype>` methods are shortcut methods that allow you to quickly fetch the definitions of clients, labels, branches, etc. They're equivalent to:

```
p4.format_spec( "<spectype>", aHash )
```

p4.handler= aHandler -> aHandler

Set the current output handler. This should be a subclass of `P4::OutputHandler`.

p4.handler -> aHandler

Get the current output handler.

p4.host= aString -> aString

Set the name of the current host. If not called, defaults to the value of `P4HOST` taken from any `P4CONFIG` file present, or from the environment as per the usual Perforce convention. Must be called before connecting to the Perforce server.

```
p4 = P4.new
p4.host = "workstation123.perforce.com"
p4.connect
...
p4.disconnect
```

p4.host -> aString

Get the current hostname.

```
p4 = P4.new
puts( p4.host )
```

p4.input= (aString|aHash|anArray) -> aString|aHash|anArray

Store input for the next command.

Call this method prior to running a command requiring input from the user. When the command requests input, the specified data will be supplied to the command. Typically, commands of the form `p4 cmd -i` are invoked using the `P4#save_<spectype>()` methods, which call `P4#input()` internally; there is no need to call `P4#input()` when using the `P4#save_<spectype>()` shortcuts.

You may pass a string, a hash, or (for commands that take multiple inputs from the user) an array of strings or hashes. If you pass an array, note that the array will be shifted each time Perforce asks the user for input.

```
p4 = P4.new
p4.connect

change = p4.run_change( "-o" ).shift
change[ "Description" ] = "Autosubmitted changelist"

p4.input = change
p4.run_submit( "-i" )

p4.disconnect
```

p4.maxlocktime= anInteger -> anInteger

Limit the amount of time (in milliseconds) spent during data scans to prevent the server from locking tables for too long. Commands that take longer than the limit will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxlocktime` for information on the commands that support this limit.

```
p4 = P4.new
begin
  p4.connect
  p4.maxlocktime = 10000 # 10 seconds
  files = p4.run_sync
rescue P4Exception => ex
  p4.errors.each { |e| $stderr.puts( e ) }
ensure
  p4.disconnectend
```

p4.maxlocktime -> anInteger

Get the current maxlocktime setting.

```
p4 = P4.new
puts( p4.maxlocktime )
```

p4.maxresults= anInteger -> anInteger

Limit the number of results Perforce permits for subsequent commands. Commands that produce more than this number of results will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxresults` for information on the commands that support this limit.

```
p4 = P4.new
begin
  p4.connect
  p4.maxresults = 100
  files = p4.run_sync
rescue P4Exception => ex
  p4.errors.each { |e| $stderr.puts( e ) }
ensure
  p4.disconnect
end
```

p4.maxresults -> anInteger

Get the current `maxresults` setting.

```
p4 = P4.new
puts( p4.maxresults )
```

p4.maxscanrows= anInteger -> anInteger

Limit the number of database records Perforce will scan for subsequent commands. Commands that attempt to scan more than this number of records will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxscanrows` for information on the commands that support this limit.

```
p4 = P4.new
begin
  p4.connect
  p4.maxscanrows = 100
  files = p4.run_sync
rescue P4Exception => ex
  p4.errors.each { |e| $stderr.puts( e ) }
ensure
  p4.disconnectend
```

p4.maxscanrows -> anInteger

Get the current `maxscanrows` setting.

```
p4 = P4.new
puts( p4.maxscanrows )
```

p4.messages -> aP4::Message

Returns a message from the Perforce Server in the form of a `P4::Message` object.

```
p4 = P4.new
p4.exception_level = P4::RAISE_NONE
p4.run_sync
p4.run_sync # this second sync should return "File(s) up-to-date."
w = p4.messages[0]
puts ( w.to_s )
```

p4.p4config_file -> aString

Get the path to the current P4CONFIG file.

```
p4 = P4.new
puts( p4.p4config_file )
```

p4.parse_<spectype>(aString) -> aP4::Spec

This is equivalent to:

```
p4.parse_spec( "<spectype>", aString )
```

p4.parse_spec("<spectype>", aString) -> aP4::Spec

Parses a Perforce form (spec) in text form into a Ruby hash using the spec definition obtained from the server.

The first argument is the type of spec to parse: `client`, `branch`, `label`, and so on. The second argument is the string buffer to parse.

Note that there are shortcuts available for this method. You can use:

```
p4.parse_<spectype>( buf )
```

instead of:

```
p4.parse_spec( "<spectype>", buf )
```

Where `<spectype>` is one of `client`, `branch`, `label`, and so on.

p4.password= aString -> aString

Set your Perforce password, in plain text. If not used, takes the value of `P4PASSWD` from any `P4CONFIG` file in effect, or from the environment according to the normal Perforce conventions. This password will also be used if you later call `p4.run_login` to login using the 2003.2 and later ticket system.

```
p4 = P4.new
p4.password = "mypass"
p4.connect
p4.run_login
```

p4.password -> aString

Get the current password or ticket. This may be the password in plain text, or if you've used `P4#run_login()`, it'll be the value of the ticket you've been allocated by the server.

```
p4 = P4.new
puts( p4.password )
```

p4.port= aString -> aString

Set the host and port of the Perforce server you want to connect to. If not called, defaults to the value of `P4PORT` in any `P4CONFIG` file in effect, and then to the value of `P4PORT` taken from the environment.

```
p4 = P4.new
p4.port = "localhost:1666"
p4.connect
...
p4.disconnect
```

p4.port -> aString

Get the host and port of the current Perforce server.

```
p4 = P4.new
puts( p4.port )
```

p4.prog= aString -> aString

Set the name of the program, as reported to Perforce system administrators running `p4 monitor show -e` in Perforce 2004.2 or later releases.

```
p4 = P4.new
p4.prog = "sync-script"
p4.connect
...
p4.disconnect
```

p4.prog -> aString

Get the name of the program as reported to the Perforce Server.

```
p4 = P4.new
p4.prog = "sync-script"
puts( p4.prog )
```

p4.progress= aProgress -> aProgress

Set the current progress indicator. This should be a subclass of **P4::Progress**.

p4.progress -> aProgress

Get the current progress indicator.

p4.run_<cmd>(arguments) -> anArray

This is equivalent to:

```
p4.run( "cmd", arguments... )
```

p4.run(aCommand, arguments...) -> anArray

Base interface to all the run methods in this API. Runs the specified Perforce command with the arguments supplied. Arguments may be in any form as long as they can be converted to strings by `to_s`.

The **P4#run()** method returns an array of results whether the command succeeds or fails; the array may, however, be empty. Whether the elements of the array are strings or hashes depends on (a) server support for tagged output for the command, and (b) whether tagged output was disabled by calling **p4.tagged = false**.

In the event of errors or warnings, and depending on the exception level in force at the time, **P4#run()** will raise a **P4Exception**. If the current exception level is below the threshold for the error/warning, **P4#run()** returns the output as normal and the caller must explicitly review **P4#errors()** and **P4#warnings()** to check for errors or warnings.

```
p4 = P4.new
p4.connect
spec = p4.run( "client", "-o" ).shift
p4.disconnect
```

Shortcuts are available for **P4#run()**. For example:

```
p4.run_command( args )
```

is equivalent to:

```
p4.run( "command", args )
```

There are also some shortcuts for common commands such as editing Perforce forms and submitting. Consequently, this:

```
p4 = P4.new
p4.connect
clientspec = p4.run_client( "-o" ).shift
clientspec[ "Description" ] = "Build client"
p4.input = clientspec
p4.run_client( "-i" )
p4.disconnect
```

may be shortened to:

```
p4 = P4.new
p4.connect
clientspec = p4.fetch_client
clientspec[ "Description" ] = "Build client"
p4.save_client( clientspec )
p4.disconnect
```

The following are equivalent:

```
p4.delete_<spectype>() p4.run( "<spectype>", "-d" )
```

```
p4.fetch_<spectype>() p4.run( "<spectype>", "-o" ).shift
```

```
p4.save_<spectype>( sp p4.input = spec p4.run( "<spectype>", "-i" )
```

As the commands associated with `P4#fetch_<spectype>()` typically return only one item, these methods do not return an array, but instead return the first result element.

For convenience in submitting changelists, changes returned by `P4#fetch_change()` can be passed to `P4#run_submit`. For example:

```
p4 = P4.new
p4.connect
spec = p4.fetch_changespec[ "Description" ] = "Automated change"
p4.run_submit( spec )
p4.disconnect
```

p4.run_filelog(fileSpec) -> anArray

Runs a `p4 filelog` on the `fileSpec` provided and returns an array of `P4::DepotFile` results when executed in tagged mode, and an array of strings when executed in non-tagged mode. By default, the raw output of `p4 filelog` is tagged; this method restructures the output into a more user-friendly (and object-oriented) form.

```
p4 = P4.new
begin
  p4.connect
  p4.run_filelog( "index.html" ).shift.each_revision do
    |r|
      r.each_integration do
        |i|
          # Do something
        end
      end
    end
  end
rescue P4Exception
  p4.errors.each { |e| puts( e ) }
ensure
  p4.disconnect
end
```

p4.run_login(arg...) -> anArray

Runs `p4 login` using a password or ticket set by the user.

p4.run_password(oldpass, newpass) -> anArray

A thin wrapper to make it easy to change your password. This method is (literally) equivalent to the following code:

```
p4.input( [ oldpass, newpass, newpass ] )
p4.run( "password" )
```

For example:

```
p4 = P4.new
p4.password = "myoldpass"
begin
  p4.connect
  p4.run_password( "myoldpass", "mynewpass" )
rescue P4Exception
  p4.errors.each { |e| puts( e ) }
ensure
  p4.disconnect
end
```

p4.run_resolve(args) [block] -> anArray

Interface to `p4 resolve`. Without a block, simply runs a non-interactive resolve (typically an automatic resolve).

```
p4.run_resolve( "-at" )
```

When a block is supplied, the block is invoked once for each merge scheduled by Perforce. For each merge, a `P4::MergeData` object is passed to the block. This object contains the context of the merge.

The block determines the outcome of the merge by evaluating to one of the following strings:

Block string	Meaning
ay	Accept Yours.
at	Accept Theirs.
am	Accept Merge result.
ae	Accept Edited result.
s	Skip this merge.
q	Abort the merge.

For example:

```
p4.run_resolve() do
  |md|
  puts( "Merging..." )
  puts( "Yours: #{md.your_name}" )
  puts( "Theirs: #{md.their_name}" )
  puts( "Base: #{md.base_name}" )
  puts( "Yours file: #{md.your_path}" )
  puts( "Theirs file: #{md.their_path}" )
  puts( "Base file: #{md.base_path}" )
  puts( "Result file: #{md.result_path}" )
  puts( "Merge Hint: #{md.merge_hint}" )

  result = md.merge_hint
  if( result == "e" )
    puts( "Invoking external merge application" )
    result = "s"      # If the merge doesn't work, we'll skip
    result = "am" if md.run_merge()
  end
  result
end
```

p4.run_submit([aHash], [arg...]) -> anArray

Submit a changelist to the server. To submit a changelist, set the fields of the changelist as required and supply any flags:.

```
change = p4.fetch_change
change._description = "Some description"
p4.run_submit( "-r", change )
```

You can also submit a changelist by supplying the arguments as you would on the command line:

```
p4.run_submit( "-d", "Some description", "somedir/..." )
```

p4.run_tickets() -> anArray

Get a list of tickets from the local tickets file. Each ticket is a hash object with fields for **Host**, **User**, and **Ticket**.

p4.save_<spectype>(hashOrString, [options]) -> anArray

The **save_<spectype>** methods are shortcut methods that allow you to quickly update the definitions of clients, labels, branches, etc. They are equivalent to:

```
p4.input = hashOrStringp4.run( "<spectype>", "-i" )
```

For example:

```
p4 = P4.new
begin
  p4.connect
  client = p4.fetch_client()
  client[ "Owner" ] = p4.user
  p4.save_client( client )
rescue P4Exception
  p4.errors.each { |e| puts( e ) }
ensure
  p4.disconnect
end
```

p4.server_case_sensitive? -> aBool

Detects whether or not the server is case-sensitive.

p4.server_level -> anInteger

Returns the current Perforce server level. Each iteration of the Perforce Server is given a level number. As part of the initial communication this value is passed between the client application and the Perforce Server. This value is used to determine the communication that the Perforce Server will understand. All subsequent requests can therefore be tailored to meet the requirements of this Server level.

For more information, see:

<http://kb.perforce.com/article/571>

p4.server_unicode? -> aBool

Detects whether or not the server is in unicode mode.

p4.set_env= (aString, aString) -> aBool

On Windows or OS X, set a variable in the registry or user preferences. To unset a variable, pass an empty string as the second argument. On other platforms, an exception is raised.

```
p4 = P4.new
p4.set_env = ( "P4CLIENT", "my_workspace" )
p4.set_env = ( "P4CLIENT", "" )
```

p4.streams= -> aBool

Enable or disable support for streams. By default, streams support is enabled at 2011.1 or higher (`P4#api_level() >= 70`). Raises a `P4Exception` if you attempt to enable streams on a pre-2011.1 server. You can enable or disable support for streams both before and after connecting to the server.

```
p4 = P4.new
p4.streams = false
```

p4.streams? -> aBool

Detects whether or not support for Perforce Streams is enabled.

```
p4 = P4.new
puts ( p4.streams? )
p4.tagged = false
puts ( p4.streams? )
```

p4.tagged(aBool) { block }

Temporarily toggles the use of tagged output for the duration of the block, and then resets it when the block terminates.

p4.tagged= aBool -> aBool

Sets tagged output. By default, tagged output is on.

```
p4 = P4.new
p4.tagged = false
```

p4.tagged? -> aBool

Detects whether or not you are in tagged mode.

```
p4 = P4.new
puts ( p4.tagged? )
p4.tagged = false
puts ( p4.tagged? )
```

p4.ticketfile= aString -> aString

Sets the location of the P4TICKETS file.

```
p4 = P4.new
p4.ticketfile = "/home/bruno/tickets"
```

p4.ticketfile -> aString

Get the path to the current P4TICKETS file.

```
p4 = P4.new
puts( p4.ticketfile )
```

p4.track= -> aBool

Instruct the server to return messages containing performance tracking information. By default, server tracking is disabled.

```
p4 = P4.new
p4.track = true
```

p4.track? -> aBool

Detects whether or not performance tracking is enabled.

```
p4 = P4.new
p4.track = true
puts ( p4.track? )
p4.track = false
puts ( p4.track? )
```

p4.track_output -> anArray

If performance tracking is enabled with **p4.track=**, returns a list of strings corresponding to the performance tracking output for the most recently-executed command.

```
p4 = P4.new
p4.track = true
p4.run_info
puts ( p4.track_output[0].slice(0,3) )    # should be "rpc"
```

p4.user= aString -> aString

Set the Perforce username. If not called, defaults to the value of **P4USER** taken from any **P4CONFIG** file present, or from the environment as per the usual Perforce convention. Must be called before connecting to the Perforce server.

```
p4 = P4.new
p4.user = "bruno"
p4.connect
...
p4.disconnect
```

p4.user -> aString

Returns the current Perforce username.

```
p4 = P4.new
puts( p4.user )
```

p4.version= aString -> aString

Set the version of your script, as reported to the Perforce Server.

p4.version -> aString

Get the version of your script, as reported to the Perforce Server.

p4.warnings -> anArray

Returns the array of warnings that arose during execution of the last command.

```
p4 = P4.new
begin
  p4.connect
  p4.exception_level( P4::RAISE_ALL ) # File(s) up-to-date is a warning
  files = p4.run_sync
rescue P4Exception => ex
  p4.warnings.each { |w| puts( w ) }
ensure
  p4.disconnect
end
```

Class P4Exception

Shallow subclass of `RuntimeError` to be used for catching Perforce-specific errors. Doesn't contain any extra information. See `P4#errors()` and `P4#warnings` for details of the errors giving rise to the exception.

Class Methods

None.

Instance Methods

None.

Class P4::DepotFile

Description

Utility class providing easy access to the attributes of a file in a Perforce depot. Each **P4::DepotFile** object contains summary information about the file, and a list of revisions (**P4::Revision** objects) of that file. Currently, only the **P4#run_filelog()** method returns an array of **P4::DepotFile** objects.

Class Methods

None.

Instance Methods

df.depot_file -> aString

Returns the name of the depot file to which this object refers.

df.each_revision { |rev| block } -> revArray

Iterates over each revision of the depot file.

df.revisions -> aArray

Returns an array of revisions of the depot file.

Class P4::Revision

Description

Utility class providing easy access to the revisions of a file in a Perforce depot. **P4::Revision** objects can store basic information about revisions and a list of the integrations for that revision. Created by `P4#run_filelog()`.

Class Methods

None.

Instance Methods

rev.action -> aString

Returns the name of the action which gave rise to this revision of the file.

rev.change -> aNumber

Returns the change number that gave rise to this revision of the file.

rev.client -> aString

Returns the name of the client from which this revision was submitted.

rev.depot_file -> aString

Returns the name of the depot file to which this object refers.

rev.desc -> aString

Returns the description of the change which created this revision. Note that only the first 31 characters are returned unless you use `p4 filelog -L` for the first 250 characters, or `p4 filelog -l` for the full text.

rev.digest -> aString

Returns the MD5 digest for this revision of the file.

rev.each_integration { |integ| block } -> integArray

Iterates over each the integration records for this revision of the depot file.

rev.filesize -> aNumber

Returns size of this revision.

rev.integrations -> integArray

Returns the list of integrations for this revision.

rev.rev -> aNumber

Returns the number of this revision of the file.

rev.time -> aTime

Returns the date /time that this revision was created.

rev.type -> aString

Returns this revision's Perforce filetype.

rev.user -> aString

Returns the name of the user who created this revision.

Class P4::Integration

Description

Utility class providing easy access to the details of an integration record. Created by `P4#run_filelog()`.

Class Methods

None.

Instance Methods

integ.how -> aString

Returns the type of the integration record - how that record was created.

integ.file -> aPath

Returns the path to the file being integrated to/from.

integ.srev -> aNumber

Returns the start revision number used for this integration.

integ.erev -> aNumber

Returns the end revision number used for this integration.

Class P4::Map

Description

The `P4::Map` class allows users to create and work with Perforce mappings, without requiring a connection to a Perforce server.

Class Methods

Map.new ([anArray]) -> aMap

Constructs a new `P4::Map` object.

Map.join (map1, map2) -> aMap

Join two `P4::Map` objects and create a third.

The new map is composed of the left-hand side of the first mapping, as joined to the right-hand side of the second mapping. For example:

```
# Map depot syntax to client syntax
client_map = P4::Map.new
client_map.insert( "//depot/main/...", "//client/..." )

# Map client syntax to local syntax
client_root = P4::Map.new
client_root.insert( "//client/...", "/home/bruno/workspace/..." )

# Join the previous mappings to map depot syntax to local syntax
local_map = P4::Map.join( client_map, client_root )
local_path = local_map.translate( "//depot/main/www/index.html" )

# local_path is now /home/bruno/workspace/www/index.html
```

Instance Methods

map.clear -> true

Empty a map.

map.count -> anInteger

Return the number of entries in a map.

map.empty? -> aBool

Test whether a map object is empty.

map.insert(aString, [aString]) -> aMap

Inserts an entry into the map.

May be called with one or two arguments. If called with one argument, the string is assumed to be a string containing either a half-map, or a string containing both halves of the mapping. In this form, mappings with embedded spaces must be quoted. If called with two arguments, each argument is assumed to be half of the mapping, and quotes are optional.

```
# called with two arguments:
map.insert( "//depot/main/...", "//client/..." )

# called with one argument containing both halves of the mapping:
map.insert( "//depot/live/... //client/live/..." )

# called with one argument containing a half-map:
# This call produces the mapping "depot/... depot/..."
map.insert( "depot/..." )
```

map.translate (aString, [aBool])-> aString

Translate a string through a map, and return the result. If the optional second argument is true, translate forward, and if it is false, translate in the reverse direction. By default, translation is in the forward direction.

map.includes? (aString) -> aBool

Tests whether a path is mapped or not.

```
if( map.includes?( "//depot/main/..." ) )
  ...
end
```

map.reverse -> aMap

Return a new `P4::Map` object with the left and right sides of the mapping swapped. The original object is unchanged.

map.lhs -> anArray

Returns the left side of a mapping as an array.

map.rhs -> anArray

Returns the right side of a mapping as an array.

map.to_a -> anArray

Returns the map as an array.

Class P4::MergeData

Description

Class containing the context for an individual merge during execution of a `p4 resolve`.

Class Methods

None.

Instance Methods

md.your_name() -> aString

Returns the name of "your" file in the merge. This is typically a path to a file in the workspace.

```
p4.run_resolve() do
  |md|
    yours = md.your_name
    md.merge_hint # merge result
end
```

md.their_name() -> aString

Returns the name of "their" file in the merge. This is typically a path to a file in the depot.

```
p4.run_resolve() do
  |md|
    theirs = md.their_name
    md.merge_hint # merge result
end
```

md.base_name() -> aString

Returns the name of the "base" file in the merge. This is typically a path to a file in the depot.

```
p4.run_resolve() do
  |md|
    base = md.base_name
    md.merge_hint # merge result
end
```

md.your_path() -> aString

Returns the path of "your" file in the merge. This is typically a path to a file in the workspace.

```
p4.run_resolve() do
  |md|
  your_path = md.your_path
  md.merge_hint # merge result
end
```

md.their_path() -> aString

Returns the path of "their" file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `P4::MergeData#their_name()` have been loaded.

```
p4.run_resolve() do
  |md|
  their_name = md.their_name
  their_file = File.open( md.their_path )
  md.merge_hint # merge result
end
```

md.base_path() -> aString

Returns the path of the base file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `P4::MergeData#base_name()` have been loaded.

```
p4.run_resolve() do
  |md|
  base_name = md.base_name
  base_file = File.open( md.base_path )
  md.merge_hint # merge result
end
```

md.result_path() -> aString

Returns the path to the merge result. This is typically a path to a temporary file on your local machine in which the contents of the automatic merge performed by the server have been loaded.

```
p4.run_resolve() do
  |md|
  result_file = File.open( md.result_path )
  md.merge_hint # merge resultend
```

md.merge_hint() -> aString

Returns the hint from the server as to how it thinks you might best resolve this merge.

```
p4.run_resolve() do
  |md|
  puts ( md.merge_hint ) # merge result
end
```

md.run_merge() -> aBool

If the environment variable **P4MERGE** is defined, **P4::MergeData#run_merge()** invokes the specified program and returns a boolean based on the return value of that program.

```
p4.run_resolve() do
  |md|
  if ( md.run_merge() )
    "am"
  else
    "s"
  end
end
```

Class P4::Message

Description

P4::Message objects contain error or other diagnostic messages from the Perforce Server; retrieve them by using the **P4#messages()** method.

Script writers can test the severity of the messages in order to determine if the server message consisted of command output (**E_INFO**), warnings, (**E_WARN**), or errors (**E_FAILED**/**E_FATAL**).

Class methods

None.

Instance methods

message.severity() -> **anInteger**

Severity of the message, which is one of the following values:

Value	Meaning
E_EMPTY	No error
E_INFO	Informational message only
E_WARN	Warning message only
E_FAILED	Command failed
E_FATAL	Severe error; cannot continue.

message.generic() -> **anInteger**

Returns the generic class of the error.

message.msgid() -> **anInteger**

Returns the unique ID of the message.

message.to_s() -> **aString**

Converts the message into a string.

message.inspect() -> **aString**

To facilitate debugging, returns a string that holds a formatted representation of the entire **P4::Message** object.

Class P4::OutputHandler

Description

The `P4::OutputHandler` class is a handler class that provides access to streaming output from the server. After defining the output handler, set `P4#handler()` to an instance of a subclass of `P4::OutputHandler` (or use a `p4.with_handler( handler )` block) to enable callbacks.

By default, `P4::OutputHandler` returns `P4::REPORT` for all output methods. The different return options are:

Value	Meaning
<code>P4::REPORT</code>	Messages added to output.
<code>P4::HANDLED</code>	Output is handled by class (don't add message to output).
<code>P4::CANCEL</code>	Operation is marked for cancel, message is added to output.

Class Methods

new P4::MyHandler.new -> aP4::OutputHandler

Constructs a new subclass of `P4::OutputHandler`.

Instance Methods

outputBinary -> int

Process binary data.

outputInfo -> int

Process tabular data.

outputMessage -> int

Process informational or error messages.

outputStat -> int

Process tagged data.

outputText -> int

Process text data.

Class P4::Progress

Description

The **P4::Progress** class is a handler class that provides access to progress indicators from the server. After defining the output handler, set **P4#progress()** to an instance of a subclass of **P4::Progress** (or use a **p4.with_progress(progress)** block) to enable callbacks.

You must implement all five of the following methods: **init()**, **description()**, **update()**, **total()**, and **done()**, even if the implementation consists of trivially returning 0.

Class Methods

new P4::MyProgress.new -> aP4::Progress

Constructs a new subclass of **P4::Progress**.

Instance Methods

init -> int

Initialize progress indicator.

description -> int

Description and type of units to be used for progress reporting.

update -> int

If non-zero, user has requested a cancellation of the operation.

total -> int

Total number of units expected (if known).

done -> int

If non-zero, operation has failed.

Class P4::Spec

Description

The `P4::Spec` class is a hash containing key / value pairs for all the fields in a Perforce form. It provides two things over and above its parent class (Hash):

- Fieldname validation. Only valid field names may be set in a `P4::Spec` object. Note that only the field name is validated, not the content.
- Accessor methods for easy access to the fields.

Class Methods

`new P4::Spec.new( anArray ) -> aP4::Spec`

Constructs a new `P4::Spec` object given an array of valid fieldnames.

Instance Methods

`spec._<fieldname> -> aValue`

Returns the value associated with the field named `<fieldname>`. This is equivalent to `spec[ "<fieldname>" ]` with the exception that when used as a method, the fieldnames may be in lowercase regardless of the actual case of the fieldname.

```
client = p4.fetch_client()
root   = client._root
desc   = client._description
```

`spec._<fieldname>= aValue -> aValue`

Updates the value of the named field in the spec. Raises a `P4Exception` if the fieldname is not valid for specs of this type.

```
client          = p4.fetch_client()
client._root    = "/home/bruno/new-client"
client._description = "My new client spec"
p4.save_client( client )
```

`spec.permitted_fields -> anArray`

Returns an array containing the names of fields that are valid in this spec object. This does not imply that values for all of these fields are actually set in this object, merely that you may choose to set values for any of these fields if you want to.

```
client = p4.fetch_client()
spec.permitted_fields.each do
  | field |
    printf ( "%14s = %s\n", field, client[ field ] )
end
```


Introduction

P4Perl is a Perl module that provides an object-oriented API to the Perforce version management system. Using P4Perl is faster than using the command-line interface in scripts, because multiple command can be executed on a single connection, and because it returns the Perforce Server's responses as Perl hashes and arrays.

The main features are:

- Get Perforce data and forms in hashes and arrays.
- Edit Perforce forms by modifying hashes.
- Run as many commands on a connection as required.
- The output of commands is returned as a Perl array.
- The elements of the array returned are strings or, where appropriate, hash references.

The most recent release of P4Perl is 2014.1.

System Requirements

P4Perl is supported on Windows, Linux, Solaris, OS X, and FreeBSD. To build P4Perl, your development machine must also have:

- Perl 5.12, 5.14, or 5.16 (ActivePerl on Windows) development files.
- `make` (or `nmake` on Windows)
- The 2014.1 Perforce C/C++ API for your target platform. Older releases might work, but are not supported.
- The same C++ compiler used to build the Perforce C++ API on your target platform.

(If you get "unresolved symbol" errors when building or running P4Perl, you probably used the wrong compiler or the wrong Perforce API build.)

Installing P4Perl

You can download P4Perl from the Perforce web site:

<http://www.perforce.com/product/components/apis>

After downloading, you can either run the installer or build the interface from source, as described in the release notes.

Programming with P4Perl

The following example shows how to connect to a Perforce server, run a `p4 info` command, and open a file for edit.

```
use P4;
my $p4 = new P4;
$p4->SetClient( $clientname );
$p4->SetPort( $p4port );
$p4->SetPassword( $p4password );
$p4->Connect()
    or die( "Failed to connect to Performer Server" );

my $info = $p4->Run( "info" );
$p4->RunEdit( "file.txt" );
die( "Failed to edit file.txt" )
    if $p4->ErrorCount()
    or $p4->WarningCount;

$p4->Disconnect();
```

Connecting to Performer over SSL

Scripts written with P4Perl use any existing **P4TRUST** file present in their operating environment (by default, **.p4trust** in the home directory of the user that runs the script).

If the fingerprint returned by the server fails to match the one installed in the **P4TRUST** file associated with the script's run-time environment, your script will (and should!) fail to connect to the server.

P4Perl Classes

The P4 module consists of several public classes:

- [“P4” on page 51](#)
- [“P4::DepotFile” on page 54](#)
- [“P4::Revision” on page 54](#)
- [“P4::Integration” on page 55](#)
- [“P4::Map” on page 55](#)
- [“P4::MergeData” on page 56](#)
- [“P4::Message” on page 57](#)
- [“P4::OutputHandler” on page 57](#)
- [“P4::Progress” on page 57](#)
- [“P4::Spec” on page 58](#)

The following tables provide brief details about each public class.

P4

The main class used for executing Perforce commands. Almost everything you do with P4Perl will involve this class.

Method	Description
new()	Construct a new P4 object.
Identify()	Print build information including P4Perl version and Perforce API version.
ClearHandler()	Clear the output handler.
Connect()	Initialize the Perforce client and connect to the Server.
Disconnect()	Disconnect from the Perforce Server.
ErrorCount()	Returns the number of errors encountered during execution of the last command.
Errors()	Returns a list of the error strings received during execution of the last command.
Fetch<Spectype>()	Shorthand for running: <pre>\$p4->Run("<spectype>", "-o");</pre>
Format<Spectype>()	Shorthand for running: <pre>\$p4->FormatSpec("<spectype>", hash);</pre>
FormatSpec()	Converts a Perforce form of the specified type (client/label etc.) held in the supplied hash into its string representation.
GetApiLevel()	Get current API compatibility level.
GetCharset()	Get character set when connecting to Unicode servers.
GetClient()	Get current client workspace (P4CLIENT).
GetCwd()	Get current working directory.
GetEnv()	Get the value of a Perforce environment variable, taking into account P4CONFIG files and (on Windows or OS X) the registry or user preferences.
GetHandler()	Get the output handler.
GetHost()	Get the current hostname.

Method	Description
<code>GetMaxLockTime()</code>	Get <code>MaxLockTime</code> used for all following commands.
<code>GetMaxResults()</code>	Get <code>MaxResults</code> used for all following commands.
<code>GetMaxScanRows()</code>	Get <code>MaxScanRows</code> used for all following commands.
<code>GetPassword()</code>	Get the current password or ticket.
<code>GetPort()</code>	Get host and port (<code>P4PORT</code>).
<code>GetProg()</code>	Get the program name as shown by the <code>p4 monitor show -e</code> command.
<code>GetProgress()</code>	Get the progress indicator.
<code>GetTicketFile()</code>	Get the location of the <code>P4TICKETS</code> file.
<code>GetUser()</code>	Get the current username (<code>P4USER</code>).
<code>GetVersion()</code>	Get the version of your script, as reported to the Perforce Server.
<code>IsConnected()</code>	Test whether or not session has been connected and/or has been dropped.
<code>IsStreams()</code>	Test whether or not streams are enabled.
<code>IsTagged()</code>	Test whether or not tagged output is enabled.
<code>IsTrack()</code>	Test whether or not server performance tracking is enabled.
<code>Iterate<Spectype>()</code>	Iterate through spec results.
<code>Messages()</code>	Return an array of <code>P4::Message</code> objects, one for each message sent by the server.
<code>P4ConfigFile()</code>	Get the location of the configuration file used (<code>P4CONFIG</code>).
<code>Parse<Spectype>()</code>	Shorthand for running: <pre>\$p4-ParseSpec("<spectype>", buffer);</pre>
<code>ParseSpec()</code>	Converts a Perforce form of the specified type (<code>client</code> , <code>label</code> , etc.) held in the supplied string into a hash and returns a reference to that hash.
<code>RunCmd()</code>	Shorthand for running: <pre>\$p4-Run("cmd", arg, ...);</pre>

Method	Description
Run()	Run a Perforce command and return its results. Check for errors with <code>P4::ErrorCount()</code> .
RunFilelog()	Runs a <code>p4 filelog</code> on the <code>fileSpec</code> provided and returns an array of <code>P4::DepotFile</code> objects.
RunLogin()	Runs <code>p4 login</code> using a password or ticket set by the user.
RunPassword()	A thin wrapper for changing your password.
RunResolve()	Interface to <code>p4 resolve</code> .
RunSubmit()	Submit a changelist to the server.
RunTickets()	Get a list of tickets from the local tickets file.
Save<Spectype>()	Shorthand for running: <pre>\$p4->SetInput(\$spectype); \$p4->Run("<spectype>", "-i");</pre>
ServerCaseSensitive()	Returns an integer specifying whether or not the server is case-sensitive.
ServerLevel()	Returns an integer specifying the server protocol level.
ServerUnicode()	Returns an integer specifying whether or not the server is in Unicode mode.
SetApiLevel()	Specify the API compatibility level to use for this script.
SetCharset()	Set character set when connecting to Unicode servers.
SetClient()	Set current client workspace (<code>P4CLIENT</code>).
SetCwd()	Set current working directory.
SetEnv()	On Windows or OS X, set an environment variable in the registry or user preferences.
SetHandler()	Set the output handler.
SetHost()	Set the name of the current host (<code>P4HOST</code>).
SetInput()	Save the supplied argument as input to be supplied to a subsequent command.
SetMaxLockTime()	Set <code>MaxLockTime</code> used for all following commands.
SetMaxResults()	Set <code>MaxResults</code> used for all following commands.

Method	Description
SetMaxScanRows()	Set MaxScanRows used for all following commands.
SetPassword()	Set Perforce password (P4PASSWD).
SetPort()	Set host and port (P4PORT).
SetProg()	Set the program name as shown by the p4 monitor show -e command.
SetProgress()	Set the progress indicator.
SetStreams()	Enable or disable streams support.
SetTicketFile()	Set the location of the P4TICKETS file.
SetTrack()	Activate or deactivate server performance tracking. By default, tracking is off (0).
SetUser()	Set the Perforce username (P4USER).
SetVersion()	Set the version of your script, as reported to the Perforce Server.
Tagged()	Toggles tagged output (1 or 0). By default, tagged output is on (1).
TrackOutput()	If performance tracking is enabled with SetTrack() returns an array of strings with tracking output.
WarningCount()	Returns the number of warnings issued by the last command.
Warnings()	Returns a list of the warning strings received during execution of the last command.

P4::DepotFile

Utility class allowing access to the attributes of a file in the depot. Returned by **P4::RunFilelog()**.

Method	Description
DepotFile()	Name of the depot file to which this object refers.
Revisions()	Returns an array of revision objects for the depot file.

P4::Revision

Utility class allowing access to the attributes of a revision of a file in the depot. Returned by **P4::RunFilelog()**.

Method	Description
Action()	Returns the action that created the revision.

Method	Description
Change()	Returns the changelist number that gave rise to this revision of the file.
Client()	Returns the name of the client from which this revision was submitted.
DepotFile()	Returns the name of the depot file to which this object refers.
Desc()	Returns the description of the change which created this revision.
Digest()	Returns the MD5 digest for this revision.
FileSize()	Returns the size of this revision.
Integrations()	Returns an array of P4::Integration objects representing all integration records for this revision.
Rev()	Returns the number of this revision.
Time()	Returns date/time this revision was created.
Type()	Returns the Perforce filetype of this revision.
User()	Returns the name of the user who created this revision.

P4::Integration

Utility class allowing access to the attributes of an integration record for a revision of a file in the depot. Returned by **P4::RunFilelog()**.

Method	Description
How()	Integration method (merge/branch/copy/ignored).
File()	Integrated file.
SRev()	Start revision.
ERev()	End revision.

P4::Map

A class that allows users to create and work with Perforce mappings without requiring a connection to the Perforce Server.

Method	Description
New()	Construct a new Map object (class method).
Join()	Joins two maps to create a third (class method).

Method	Description
Clear()	Empties a map.
Count()	Returns the number of entries in a map.
IsEmpty()	Tests whether or not a map object is empty.
Insert()	Inserts an entry into the map.
Translate()	Translate a string through a map.
Includes()	Tests whether a path is mapped.
Reverse()	Returns a new mapping with the left and right sides reversed.
Lhs()	Returns the left side as an array.
Rhs()	Returns the right side as an array.
AsArray()	Returns the map as an array.

P4::MergeData

Class encapsulating the context of an individual merge during execution of a **p4 resolve** command. Passed to [P4::RunResolve](#).

Method	Description
YourName()	Returns the name of "your" file in the merge. (file in workspace)
TheirName()	Returns the name of "their" file in the merge. (file in the depot)
BaseName()	Returns the name of "base" file in the merge. (file in the depot)
YourPath()	Returns the path of "your" file in the merge. (file in workspace)
TheirPath()	Returns the path of "their" file in the merge. (temporary file on workstation into which TheirName() has been loaded)
BasePath()	Returns the path of the base file in the merge. (temporary file on workstation into which BaseName() has been loaded)
ResultPath()	Returns the path to the merge result. (temporary file on workstation into which the automatic merge performed by the server has been loaded)
MergeHint()	Returns hint from server as to how user might best resolve merge.
RunMergeTool()	If the environment variable P4MERGE is defined, run it and indicate whether or not the merge tool successfully executed.

P4::Message

Class encapsulating the context of an individual error during execution of Perforce commands. Passed to [P4::Messages\(\)](#).

Method	Description
GetSeverity()	Returns the severity class of the error.
GetGeneric()	Returns the generic class of the error message.
GetId()	Returns the unique ID of the error message.
GetText()	Get the text of the error message.

P4::OutputHandler

Handler class that provides access to streaming output from the server; call [P4::SetHandler\(\)](#) with an implementation of `P4::OutputHandler` to enable callbacks:

Method	Description
OutputBinary()	Process binary data.
OutputInfo()	Process tabular data.
OutputMessage()	Process information or errors.
OutputStat()	Process tagged output.
OutputText()	Process text data.

P4::Progress

Handler class that provides access to progress indicators from the server; call [P4::SetProgress\(\)](#) with an implementation of `P4::Progress` to enable callbacks:

Method	Description
Init()	Initialize progress indicator as designated type.
Total()	Total number of units (if known).
Description()	Description and type of units to be used for progress reporting.
Update()	If non-zero, user has requested a cancellation of the operation.
Done()	If non-zero, operation has failed.

P4::Resolver

Class for handling resolves in Perforce.

Method	Description
Resolve()	Perform a resolve and return the resolve decision as a string.

P4::Spec

Utility class allowing access to the attributes of the fields in a Perforce form.

Method	Description
_fieldname()	Return the value associated with the field named <i>fieldname</i> .
_fieldname()	Set the value associated with the field named <i>fieldname</i> .
PermittedFields()	Lists the fields that are permitted for specs of this type.

Class P4

Description

Main interface to the Perforce client API.

This module provides an object-oriented interface to the Perforce version management system. Data is returned in Perl arrays and hashes and input can also be supplied in these formats.

Each **P4** object represents a connection to the Perforce Server, and multiple commands may be executed (serially) over a single connection.

The basic model is to:

1. Instantiate your **P4** object.
2. Specify your Perforce client environment.

- **SetClient()**
 - **SetHost()**
 - **SetPassword()**
 - **SetPort()**
 - **SetUser()**

3. Connect to the Perforce service.

The Perforce protocol is not designed to support multiple concurrent queries over the same connection. Multithreaded applications that use the C++ API or derived APIs (including P4Perl) should ensure that a separate connection is used for each thread, or that only one thread may use a shared connection at a time.

4. Run your Perforce commands.
5. Disconnect from the Perforce service.

Class methods

P4::new() -> **P4**

Construct a new **P4** object. For example:

```
my $p4 = new P4;
```

P4::Identify() -> **string**

Print build information including P4Perl version and Perforce API version.

```
print P4::Identify();
```

The constants `OS`, `PATCHLEVEL` and `VERSION` are also available to test an installation of P4Perl without having to parse the output of `P4::Identify()`. Also reports the version of the OpenSSL library used for building the underlying Perforce C++ API with which P4Perl was built.

P4::ClearHandler() -> undef

Clear any configured output handler.

P4::Connect() -> bool

Initializes the Perforce client and connects to the server. Returns **false** on failure and **true** on success.

P4::Disconnect() -> undef

Terminate the connection and clean up. Should be called before exiting.

P4::ErrorCount() -> integer

Returns the number of errors encountered during execution of the last command.

P4::Errors() -> list

Returns a list of the error strings received during execution of the last command.

P4::Fetch<Spectype>([name]) -> hashref

Shorthand for running:

```
$p4->Run( "<spectype>", "-o" );
```

and returning the first element of the result array. For example:

```
$label      = $p4->FetchLabel( $labelname );  
$change     = $p4->FetchChange( $changenno );  
$clientspec = $p4->FetchClient( $clientname );
```

P4::Format<Spectype>(hash) -> string

Shorthand for running:

```
$p4->FormatSpec( "<spectype>", hash);
```

and returning the results. For example:

```
$change      = $p4->FetchChange();  
$change->{ 'Description' } = 'Some description';  
$form       = $p4->FormatChange( $change );  
printf( "Submitting this change:\n\n%s\n", $form );  
$p4->RunSubmit( $change );
```

P4::FormatSpec(\$spectype, \$string) -> string

Converts a Perforce form of the specified type (`client`, `label`, etc.) held in the supplied hash into its string representation. Shortcut methods are available that obviate the need to supply the type argument. The following two examples are equivalent:

```
my $client = $p4->FormatSpec( "client", $hash );
```

```
my $client = $p4->FormatClient( $hash );
```

P4::GetApiLevel() -> integer

Returns the current API compatibility level. Each iteration of the Perforce Server is given a level number. As part of the initial communication, the client protocol level is passed between client application and the Perforce Server. This value, defined in the Perforce API, determines the communication protocol level that the Perforce client will understand. All subsequent responses from the Perforce Server can be tailored to meet the requirements of that client protocol level.

For more information, see:

<http://kb.perforce.com/article/512>

P4::GetCharset() -> string

Return the name of the current charset in use. Applicable only when used with Perforce servers running in unicode mode.

P4::GetClient() -> string

Returns the current Perforce client name. This may have previously been set by `P4::SetClient()`, or may be taken from the environment or `P4CONFIG` file if any. If all that fails, it will be your hostname.

P4::GetCwd() -> string

Returns the current working directory as your Perforce client sees it.

P4::GetEnv(\$var) -> string

Returns the value of a Perforce environment variable, taking into account the settings of Perforce variables in `P4CONFIG` files, and, on Windows or OS X, in the registry or user preferences.

P4::GetHandler() -> Handler

Returns the output handler.

P4::GetHost() -> string

Returns the client hostname. Defaults to your hostname, but can be overridden with `P4::SetHost()`

P4::GetMaxLockTime(\$value) -> integer

Get the current maxlocktime setting.

P4::GetMaxResults(\$value) -> integer

Get the current maxresults setting.

P4::GetMaxScanRows(\$value) -> integer

Get the current maxscanrows setting.

P4::GetPassword() -> string

Returns your Perforce password. Taken from a previous call to `P4::SetPassword()` or extracted from the environment (`$ENV{P4PASSWD}`), or a `P4CONFIG` file.

P4::GetPort() -> string

Returns the current address for your Perforce server. Taken from a previous call to `P4::SetPort()`, or from `$ENV{P4PORT}` or a `P4CONFIG` file.

P4::GetProg() -> string

Get the name of the program as reported to the Perforce Server.

P4::GetProgress() -> Progress

Returns the progress indicator.

P4::GetTicketFile([\$string]) -> string

Return the path of the current `P4TICKETS` file.

P4::GetUser() -> String

Get the current user name. Taken from a previous call to `P4::SetUser()`, or from `$ENV{P4USER}` or a `P4CONFIG` file.

P4::GetVersion(\$string) -> string

Get the version of your script, as reported to the Perforce Server.

P4::IsConnected() -> bool

Returns true if the session has been connected, and has not been dropped.

P4::IsStreams() -> bool

Returns true if streams support is enabled on this server.

P4::IsTagged() -> bool

Returns true if Tagged mode is enabled on this client.

P4::IsTrack() -> bool

Returns true if server performance tracking is enabled for this connection.

P4::Iterate<Spectype>(arguments) -> object

Iterate over spec results. Returns an iterable object with `next()` and `hasNext()` methods.

Valid <*spectype*>s are `clients`, `labels`, `branches`, `changes`, `streams`, `jobs`, `users`, `groups`, `depots` and `servers`. Valid arguments are any arguments that would be valid for the corresponding `P4::RunCmd()` command.

Arguments can be passed to the iterator to filter the results, for example, to iterate over only the first two client workspace specifications:

```
$p4->IterateClients( "-m2" );
```

You can also pass the spec type as an argument:

```
$p4->Iterate( "changes" );
```

For example, to iterate through client specs:

```
use P4;

my $p4 = P4->new;
$p4->Connect or die "Couldn't connect";
my $i = $p4->IterateClients();
while($i->hasNext) {
    my $spec = $i->next;
    print( "Client: " . ($spec->{Client} or "<undef>") . "\n" );
}
```

P4::Messages() -> list

Returns an array of `P4::Message()` objects, one for each message (info, warning or error) sent by the server.

P4::P4ConfigFile() -> string

Get the path to the current P4CONFIG file.

P4::Parse<Spectype>(\$string) -> hashref

Shorthand for running:

```
$p4->ParseSpec( "<spectype>", buffer);
```

and returning the results. For example:

```
$p4 = new P4;
$p4->Connect() or die( "Failed to connect to server" );
$client = $p4->FetchClient();

# Returns a hashref
$client = $p4->FormatClient( $client );

# Convert to string
$client = $p4->ParseClient( $client );
# Convert back to hashref
FIXME
```

Comments in forms are preserved. Comments are stored as a **comment** key in the spec hash and are accessible. For example:

```
my $spec = $pc->ParseGroup( 'my_group' );
print $spec->{'comment'};
```

P4::ParseSpec(\$spectype, \$string) -> hashref

Converts a Perforce form of the specified type (client/label etc.) held in the supplied string into a hash and returns a reference to that hash. Shortcut methods are available to avoid the need to supply the type argument. The following two examples are equivalent:

```
my $hash = $p4->ParseSpec( "client", $clientspec );
```

```
my $hash = $p4->ParseClient( $clientspec );
```

P4::Run<Cmd>([\$arg...]) -> list | arrayref

Shorthand for running:

```
$p4-Run( "cmd", arg, ...);
```

and returning the results.

P4::Run("<cmd>", [\$arg...]) -> list | arrayref

Run a Perforce command and return its results. Because Perforce commands can partially succeed and partially fail, it is good practice to check for errors using **P4::ErrorCount()**.

Results are returned as follows:

- A list of results in array context
- An array reference in scalar context

The AutoLoader enables you to treat Perforce commands as methods:

```
p4->RunEdit( "filename.txt" );
```

is equivalent to:

```
$p4->Run( "edit", "filename.txt" );
```

Note that the content of the array of results you get depends on (a) whether you're using tagged mode, (b) the command you've executed, (c) the arguments you supplied, and (d) your Perforce server version.

Tagged mode and form parsing mode are turned on by default; each result element is a hashref, but this is dependent on the command you ran and your server version.

In non-tagged mode, each result element is a string. In this case, because the Perforce server sometimes asks the client to write a blank line between result elements, some of these result elements can be empty.

Note that the return values of individual Perforce commands are not documented because they may vary between server releases.

To correlate the results returned by the P4 interface with those sent to the command line client, try running your command with RPC tracing enabled. For example:

Tagged mode: **p4 -Ztag -vrpc=1 describe -s 4321**

Non-Tagged mode: **p4 -vrpc=1 describe -s 4321**

FIXME Pay attention to the calls to **client-FstatInfo()**, **client-OutputText()**, **client-OutputData()** and **client-HandleError()**. Each call to one of these functions results in either a result element, or an error element.

P4::RunFilelog([\$args ...], \$fileSpec ...) -> list | arrayref

Runs a `p4 filelog` on the `fileSpec` provided and returns an array of `P4::DepotFile` objects when executed in tagged mode.

P4::RunLogin(...) -> list | arrayref

Runs `p4 login` using a password or ticket set by the user.

P4::RunPassword(\$oldpass, \$newpass) -> list | arrayref

A thin wrapper for changing your password from `$oldpass` to `$newpass`. Not to be confused with `P4::SetPassword()`.

P4::RunResolve([\$resolver], [\$args ...]) -> string

Run a `p4 resolve` command. Interactive resolves require the `$resolver` parameter to be an object of a class derived from `P4::Resolver`. In these cases, the `P4::Resolve()` method of this class is called to handle the resolve. For example:

```
$resolver = new MyResolver;  
$p4->RunResolve( $resolver );
```

To perform an automated merge that skips whenever conflicts are detected:

```
use P4;  
  
package MyResolver;  
our @ISA = qw( P4::Resolver );  
  
sub Resolve( $ ) {  
    my $self      = shift;  
    my $mergeData = shift;  
  
    # "s"kip if server-recommended hint is to "e"dit the file,  
    # because such a recommendation implies the existence of a conflict  
    return "s" if ( $mergeData->Hint() eq "e" );  
    return $mergeData->Hint();  
}  
1;  
  
package main;  
  
$p4 = new P4;  
$resolver = new MyResolver;  
  
$p4->Connect() or die( "Failed to connect to Perforce" );  
$p4->RunResolve( $resolver, ... );
```

In non-interactive resolves, no `P4::Resolver` object is required. For example:

```
$p4->RunResolve( "at" );
```

P4::RunSubmit(\$arg | \$hashref, ...) -> list | arrayref

Submit a changelist to the server. To submit a changelist, set the fields of the changelist as required and supply any flags:

```
$change = $p4->FetchChange();  
$change->{ 'Description' } = "Some description";  
$p4->RunSubmit( "-r", $change );
```

You can also submit a changelist by supplying the arguments as you would on the command line:

```
$p4->RunSubmit( "-d", "Some description", "somedir/..." );
```

P4::RunTickets() -> list

Get a list of tickets from the local tickets file. Each ticket is a hash object with fields for **Host**, **User**, and **Ticket**.

P4::Save<Spectype>() -> list | arrayref

Shorthand for running:

```
$p4->SetInput( $spectype );  
$p4->Run( "<spectype>", "-i");
```

For example:

```
$p4->SaveLabel( $label );  
$p4->SaveChange( $changenos );  
$p4->SaveClient( $clientspec );
```

P4::ServerCaseSensitive() -> integer

Returns an integer specifying whether or not the server is case-sensitive.

P4::ServerLevel() -> integer

Returns an integer specifying the server protocol level. This is not the same as, but is closely aligned to, the server version. To find out your server's protocol level, run `p4 -vrpc=5 info` and look for the `server2` protocol variable in the output. For more information, see:

<http://kb.perforce.com/article/571>

P4::ServerUnicode() -> integer

Returns an integer specifying whether or not the server is in Unicode mode.

P4::SetApiLevel(\$integer) -> undef

Specify the API compatibility level to use for this script. This is useful when you want your script to continue to work on newer server versions, even if the new server adds tagged output to previously unsupported commands.

The additional tagged output support can change the server's output, and confound your scripts. Setting the API level to a specific value allows you to lock the output to an older format, thus increasing the compatibility of your script.

Must be called before calling **P4::Connect()**. For example:

```
$p4->SetApiLevel( 67 ); # Lock to 2010.1 format
$p4->Connect() or die( "Failed to connect to Perforce" );
# etc.
```

P4::SetCharset(\$charset) -> undef

Specify the character set to use for local files when used with a Perforce server running in unicode mode. Do not use unless your Perforce server is in unicode mode. Must be called before calling **P4::Connect()**. For example:

```
$p4->SetCharset( "winansi" );
$p4->SetCharset( "iso8859-1" );
$p4->SetCharset( "utf8" );
# etc.
```

P4::SetClient(\$client) -> undef

Sets the name of your Perforce client workspace. If you don't call this method, then the client workspace name will default according to the normal Perforce conventions:

1. Value from file specified by **P4CONFIG**
2. Value from **\$ENV{P4CLIENT}**
3. Hostname

P4::SetCwd(\$path) -> undef

Sets the current working directory for the client.

P4::SetEnv(\$var, \$value) -> undef

On Windows or OS X, set a variable in the registry or user preferences. To unset a variable, pass an empty string as the second argument. On other platforms, an exception is raised.

```
$p4->SetEnv( "P4CLIENT", "my_workspace" );  
$P4->SetEnv( "P4CLIENT", "" );
```

P4::SetHandler(Handler) -> Handler

Sets the output handler.

P4::SetHost(\$hostname) -> undef

Sets the name of the client host, overriding the actual hostname. This is equivalent to `p4 -H hostname`, and only useful when you want to run commands as if you were on another machine.

P4::SetInput(\$string | \$hashref | \$arrayref) -> undef

Save the supplied argument as input to be supplied to a subsequent command. The input may be a hashref, a scalar string, or an array of hashrefs or scalar strings. If you pass an array, the array will be shifted once each time the Perforce command being executed asks for user input.

P4::SetMaxLockTime(\$integer) -> undef

Limit the amount of time (in milliseconds) spent during data scans to prevent the server from locking tables for too long. Commands that take longer than the limit will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxresults` for information on the commands that support this limit.

P4::SetMaxResults(\$integer) -> undef

Limit the number of results for subsequent commands to the value specified. Perforce will abort the command if continuing would produce more than this number of results. Once set, this limit remains in force unless you remove the restriction by setting it to a value of 0.

P4::SetMaxScanRows(\$integer) -> undef

Limit the number of records Perforce will scan when processing subsequent commands to the value specified. Perforce will abort the command once this number of records has been scanned. Once set, this limit remains in force unless you remove the restriction by setting it to a value of 0.

P4::SetPassword(\$password) -> undef

Specify the password to use when authenticating this user against the Perforce Server - overrides all defaults. Not to be confused with `P4::Password()`.

P4::SetPort(\$port) -> undef

Set the port on which your Perforce server is listening. Defaults to:

1. Value from file specified by `P4CONFIG`
2. Value from `$ENV{P4PORT}`

3. `perforce:1666`

P4::SetProg(\$program_name) -> undef

Set the name of your script. This value is displayed in the server log on 2004.2 or later servers.

P4::SetProgress(Progress) -> Progress

Sets the progress indicator.

P4::SetStreams(0 | 1) -> undef

Enable or disable support for streams. By default, streams support is enabled at 2011.1 or higher (`P4::GetApiLevel() >= 70`). Streams support requires a server at 2011.1 or higher. You can enable or disable support for streams both before and after connecting to the server.

P4::SetTicketFile([\$string]) -> string

Set the path to the current `P4TICKETS` file (and return it).

P4::SetTrack(0 | 1) -> undef

Enable (1) or disable (0) server performance tracking for this connection. By default, performance tracking is disabled.

P4::SetUser(\$username) -> undef

Set your Perforce username. Defaults to:

1. Value from file specified by `P4CONFIG`
2. Value from `C{$ENV{P4USER}}`
3. OS username

P4::SetVersion(\$version) -> undef

Specify the version of your script, as recorded in the Perforce server log file.

P4::Tagged(0 | 1 | \$coderef) -> undef

Enable (1) or disable (0) tagged output from the server, or temporarily toggle it.

By default, tagged output is enabled, but can be disabled (or re-enabled) by calling this method. If you provide a code reference, you can run a subroutine with the tagged status toggled for the duration of that reference. For example:

```
my $GetChangeCounter = sub{ $p4->RunCounter('change')->[ 0 ] };
my $changen0 = $p4->Tagged( 0, $GetChangeCounter );
```

When running in tagged mode, responses from commands that support tagged output will be returned in the form of a hashref. When running in non-tagged mode, responses from commands are returned in the form of strings (that is, in plain text).

P4::TrackOutput() -> list

If performance tracking is enabled with [P4::SetTrack\(\)](#), returns a list of strings corresponding to the performance tracking output of the most recently-executed command.

P4::WarningCount() -> integer

Returns the number of warnings issued by the last command.

```
$p4->WarningCount();
```

P4::Warnings() -> list

Returns a list of warning strings from the last command

```
$p4->Warnings();
```

Class P4::DepotFile

Description

P4::DepotFile objects are used to present information about files in the Perforce repository. They are returned by P4::RunFilelog().

Class Methods

None.

Instance Methods

\$df->DepotFile() -> string

Returns the name of the depot file to which this object refers.

\$df->Revisions() -> array

Returns an array of P4::Revision objects, one for each revision of the depot file.

Class P4::Revision

Description

P4::Revision objects represent individual revisions of files in the Perforce repository. They are returned as part of the output of P4::RunFilelog().

Class Methods

\$rev->Integrations() -> array

Returns an array of P4::Integration objects representing all integration records for this revision.

Instance Methods

\$rev->Action() -> string

Returns the name of the action which gave rise to this revision of the file.

\$rev->Change() -> integer

Returns the changelist number that gave rise to this revision of the file.

\$rev->Client() -> string

Returns the name of the client from which this revision was submitted.

\$rev->DepotFile() -> string

Returns the name of the depot file to which this object refers.

\$rev->Desc() -> string

Returns the description of the change which created this revision. Note that only the first 31 characters are returned unless you use `p4 filelog -L` for the first 250 characters, or `p4 filelog -l` for the full text.

\$rev->Digest() -> string

Returns the MD5 digest for this revision.

\$rev->FileSize() -> string

Returns the size of this revision.

\$rev->Rev() -> integer

Returns the number of this revision of the file.

`$rev->Time() -> string`

Returns the date / time that this revision was created.

`$rev->Type() -> string`

Returns this revision's Perforce filetype.

`$rev->User() -> string`

Returns the name of the user who created this revision.

Class P4::Integration

Description

P4::Integration objects represent Perforce integration records. They are returned as part of the output of P4::RunFilelog().

Class Methods

None.

Instance Methods

\$integ->How() -> string

Returns the type of the integration record - how that record was created.

\$integ->File() -> string

Returns the path to the file being integrated to/from.

\$integ->SRev() -> integer

Returns the start revision number used for this integration.

\$integ->ERev() -> integer

Returns the end revision number used for this integration.

Class P4::Map

Description

The `P4::Map` class allows users to create and work with Perforce mappings, without requiring a connection to a Perforce server.

Class Methods

`$map = new P4::Map( [ array ] ) -> aMap`

Constructs a new `P4::Map` object.

`$map->Join( map1, map2 ) -> aMap`

Join two `P4::Map` objects and create a third.

The new map is composed of the left-hand side of the first mapping, as joined to the right-hand side of the second mapping. For example:

```
# Map depot syntax to client syntax
$client_map = new P4::Map;
$client_map->Insert( "//depot/main/...", "//client/..." );

# Map client syntax to local syntax
$client_root = new P4::Map;
$client_root->Insert( "//client/...", "/home/bruno/workspace/..." );

# Join the previous mappings to map depot syntax to local syntax
$local_map = P4::Map::Join( $client_map, $client_root );
$local_path = $local_map->Translate( "//depot/main/www/index.html" );

# $local_path is now /home/bruno/workspace/www/index.html
```

Instance Methods

`$map->Clear() -> undef`

Empty a map.

`$map->Count() -> integer`

Return the number of entries in a map.

`$map->IsEmpty() -> bool`

Test whether a map object is empty.

\$map->Insert(string ...) -> undef

Inserts an entry into the map.

May be called with one or two arguments. If called with one argument, the string is assumed to be a string containing either a half-map, or a string containing both halves of the mapping. In this form, mappings with embedded spaces must be quoted. If called with two arguments, each argument is assumed to be half of the mapping, and quotes are optional.

```
# called with two arguments:
$map->Insert( "//depot/main/...", "//client/..." );

# called with one argument containing both halves of the mapping:
$map->Insert( "//depot/live/... //client/live/..." );

# called with one argument containing a half-map:
# This call produces the mapping "depot/... depot/..."
$map->Insert( "depot/..." );
```

\$map->Translate(string, [bool]) -> string

Translate a string through a map, and return the result. If the optional second argument is 1, translate forward, and if it is 0, translate in the reverse direction. By default, translation is in the forward direction.

\$map->Includes(string) -> bool

Tests whether a path is mapped or not.

```
if ( $map->Includes( "//depot/main/..." ) ) {
    ...
}
```

\$map->Reverse() -> aMap

Return a new `P4::Map` object with the left and right sides of the mapping swapped. The original object is unchanged.

\$map->Lhs() -> array

Returns the left side of a mapping as an array.

\$map->Rhs() -> array

Returns the right side of a mapping as an array.

\$map->AsArray() -> array

Returns the map as an array.

Class P4::MergeData

Description

Class containing the context for an individual merge during execution of a `p4 resolve`. Users may not create objects of this class; they are created internally during `P4::RunResolve()`, and passed down to the `Resolve()` method of a `P4::Resolver` subclass.

Class Methods

None.

Instance Methods

\$md>YourName() -> string

Returns the name of "your" file in the merge, in client syntax.

\$md.TheirName() -> string

Returns the name of "their" file in the merge, in client syntax, including the revision number.

\$md.BaseName() -> string

Returns the name of the "base" file in the merge, in depot syntax, including the revision number.

\$md>YourPath() -> string

Returns the path of "your" file in the merge. This is typically a path to a file in the client workspace.

\$md.TheirPath() -> string

Returns the path of "their" file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `P4::MergeData::TheirName()` have been loaded.

\$md.BasePath() -> string

Returns the path of the base file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `P4::MergeData::BaseName()` have been loaded.

\$md.ResultPath() -> string

Returns the path to the merge result. This is typically a path to a temporary file on your local machine in which the contents of the automatic merge performed by the server have been loaded.

\$md.MergeHint() -> string

Returns a string containing the hint from Perforce's merge algorithm, indicating the recommended action for performing the resolve.

\$md.RunMergeTool() -> integer

If the environment variable `P4MERGE` is defined, `P4::MergeData::RunMergeTool()` invokes the specified program and returns true if the merge tool was successfully executed, otherwise returns false.

Class P4::Message

Description

P4::Message objects contain error or other diagnostic messages from the Perforce Server; they are returned by P4::Messages().

Script writers can test the severity of the messages in order to determine if the server message consisted of command output (E_INFO), warnings, (E_WARN), or errors (E_FAILED/E_FATAL).

Class methods

None.

Instance methods

\$message.GetSeverity() -> int

Severity of the message, which is one of the following values:

Value	Meaning
E_EMPTY	No error.
E_INFO	Informational message only.
E_WARN	Warning message only.
E_FAILED	Command failed.
E_FATAL	Severe error; cannot continue.

\$message.GetGeneric() -> int

Returns the generic class of the error.

\$message.GetId() -> int

Returns the unique ID of the message.

\$message.GetText() -> int

Converts the message into a string.

Class P4::OutputHandler

Description

The `P4::OutputHandler` class provides access to streaming output from the server. After defining the output handler, call `P4::SetHandler()` with your implementation of `P4::OutputHandler`.

Because P4Perl does not provide a template or superclass, your output handler must implement all five of the following methods: `OutputMessage()`, `OutputText()`, `OutputInfo()`, `OutputBinary()`, and `OutputStat()`, even if the implementation consists of trivially returning 0 (report only: don't handle output, don't cancel operation).

These methods must return one of the following four values:

Value	Meaning
0	Messages added to output (don't handle, don't cancel).
1	Output is handled by class (don't add message to output).
2	Operation is marked for cancel, message is added to output.
3	Operation is marked for cancel, message not added to output.

Class Methods

None.

Instance Methods

`$handler.OutputBinary() -> int`

Process binary data.

`$handler.OutputInfo() -> int`

Process tabular data.

`$handler.OutputMessage() -> int`

Process informational or error messages.

`$handler.OutputStat()-> int`

Process tagged data.

`$handler.OutputText() -> int`

Process text data.

Class P4::Progress

Description

The `P4::Progress` provides access to progress indicators from the server. After defining the progress class, call `P4::SetProgress()` with your implementation of `P4::Progress`.

Because P4Perl does not provide a template or superclass, you must implement all five of the following methods: `Init()`, `Description()`, `Update()`, `Total()`, and `Done()`, even if the implementation consists of trivially returning 0.

Class Methods

None.

Instance Methods

`$progress.Init() -> int`

Initialize progress indicator.

`$progress.Description( string, int ) -> int`

Description and type of units to be used for progress reporting.

`$progress.Update() -> int`

If non-zero, user has requested a cancellation of the operation.

`$progress.Total()-> int`

Total number of units expected (if known).

`$progress.Done() -> int`

If non-zero, operation has failed.

Class P4::Resolver

Description

P4::Resolver is a class for handling resolves in Perforce. It is intended to be subclassed, and for subclasses to override the **Resolve()** method. When **P4::RunResolve()** is called with a **P4::Resolver** object, it calls the **P4::Resolver::Resolve()** method of the object once for each scheduled resolve.

Class Methods

None.

Instance Methods

\$resolver.Resolve() -> string

Returns the resolve decision as a string. The standard Perforce resolve strings apply:

String	Meaning
ay	Accept Yours.
at	Accept Theirs.
am	Accept Merge result.
ae	Accept Edited result.
s	Skip this merge.
q	Abort the merge.

By default, all automatic merges are accepted, and all merges with conflicts are skipped. The **P4::Resolver::Resolve()** method is called with a single parameter, which is a reference to a **P4::MergeData** object.

Class P4::Spec

Description

P4::Spec objects provide easy access to the attributes of the fields in a Perforce form.

The P4::Spec class uses Perl's AutoLoader to simplify form manipulation. Form fields can be accessed by calling a method with the same name as the field prefixed by an underscore (`_`).

Class Methods

\$spec = new P4::Spec(\$fieldMap) -> array

Constructs a new P4::Spec object for a form containing the specified fields. (The object also contains a `_fields_` member that stores a list of field names that are valid in forms of this type.)

Instance Methods

\$spec->_<fieldname> -> string

Returns the value associated with the field named *<fieldname>*.

```
$client = $p4->FetchClient( $clientname );
$client->_Root();    # Get client root
```

\$spec->_<fieldname>(\$string)-> string

Updates the value of the named field in the spec.

```
$client = $p4->FetchClient( $clientname );
$client->_Root( $newroot );    # Set client root
```

\$spec->PermittedFields() -> array

Returns an array containing the names of fields that are valid in this spec object. This does not imply that values for all of these fields are actually set in this object, merely that you may choose to set values for any of these fields if you want to.

```
my $client = $p4->FetchClient( $clientname );
my @fields = $p4->PermittedFields( $client );
foreach $field (@fields) {
    print "$field\n";
}
```

Introduction

P4Python, the Python interface to the Perforce API, enables you to write Python code that interacts with a Perforce server. P4Python enables your Python scripts to:

- Get Perforce data and forms in dictionaries and lists.
- Edit Perforce forms by modifying dictionaries.
- Provide exception-based error handling and optionally ignore warnings.
- Issue multiple commands on a single connection (performs better than spawning single commands and parsing the results).

The most recent release of P4Python is 2015.1.

System Requirements

P4Python is supported on Windows, Linux, Solaris, OS X, and FreeBSD.

To build P4Python from source, your development machine must also have:

- Python 2.7 or 3.3 development files.
- The 2015.1 Perforce C/C++ API for your target platform.
- The same C++ compiler used to build the Perforce C++ API on your target platform.

(If you get "unresolved symbol" errors when building or running P4Python, you probably used the wrong compiler or the wrong Perforce API build.)

For the most up-to-date system requirements, see the P4Python release notes:

<http://www.perforce.com/perforce/r15.1/user/p4pythonnotes.txt>

Installing P4Python

Important

Before installing P4Python, any previously installed versions should be uninstalled.

As of P4Python 2015.1, the recommended mechanism for installing P4Python is via **pip**. For example:

```
$ pip install p4python
```

pip installs binary versions of P4Python where possible, otherwise it attempts to automatically build P4Python from source.

Windows users can download an installer containing pre-built packages for P4Python from the Perforce web site:

<http://www.perforce.com/product/components/apis>

Note

When P4Python is built without the `--apidir` option, setup attempts to connect to ftp.perforce.com to download the correct version of the P4API binary. If the P4API download is successful, it is unpacked into a temporary directory.

When P4Python is built and the `--ssl` is provided without a path, setup attempts to determine the correct path of the installed OpenSSL libraries by executing `openssl version`.

Programming with P4Python

P4Python provides an object-oriented interface to Perforce that is intended to be intuitive for Python programmers. Data is loaded and returned in Python arrays and dictionaries. Each **P4** object represents a connection to the Perforce server.

When instantiated, the **P4** instance is set up with the default environment settings just as the command line client **p4**, that is, using environment variables, the registry or user preferences (on Windows and OS X) and, if defined, the **P4CONFIG** file. The settings can be checked and changed before the connection to the server is established with the **P4.connect()** method. After your script connects, it can send multiple commands to the Perforce server with the same **P4** instance. After the script is finished, it should disconnect from the server by calling the **P4.disconnect()** method.

The following example illustrates the basic structure of a P4Python script. The example establishes a connection, issues a command, and tests for errors resulting from the command.

```
from P4 import P4,P4Exception    # Import the module
p4 = P4()                        # Create the P4 instance
p4.port = "1666"
p4.user = "fred"
p4.client = "fred-ws"            # Set some environment variables

try:                             # Catch exceptions with try/except
    p4.connect()                 # Connect to the Perforce server
    info = p4.run( "info" )      # Run "p4 info" (returns a dict)
    for key in info[0]:          # and display all key-value pairs
        print key, "=", info[0][key]
    p4.run( "edit", "file.txt" ) # Run "p4 edit file.txt"
    p4.disconnect()             # Disconnect from the server
except P4Exception:
    for e in p4.errors:          # Display errors
        print e
```

This example creates a client workspace from a template and syncs it:.

```
from P4 import P4, P4Exception

template = "my-client-template"
client_root = "C:\\work\\my-root"
p4 = P4()

try:
    p4.connect()
    # Convert client spec into a Python dictionary
    client = p4.fetch_client( "-t", template )
    client._root = client_root
    p4.save_client( client )
    p4.run_sync()

except P4Exception:
    # If any errors occur, we'll jump in here. Just log them
    # and raise the exception up to the higher level
```

Submitting a Changelist

This example creates a changelist, modifies it and then submits it:.

```
from P4 import P4

p4 = P4()
p4.connect()
change = p4.fetch_change()

# Files were opened elsewhere and we want to
# submit a subset that we already know about.

myfiles = ['//depot/some/path/file1.c', '//depot/some/path/file1.h']
change._description = "My changelist\nSubmitted from P4Python\n"
change._files = myfiles # This attribute takes a Python list
p4.run_submit( change )
```

Logging into Perforce using ticket-based authentication

On some servers, users might need to log in to Perforce before issuing commands. The following example illustrates login using Perforce tickets.

```
from P4 import P4

p4 = P4()
p4.user = "bruno"
p4.password = "my_password"
p4.connect()
p4.run_login()
opened = p4.run_opened()

...
```

Connecting to Perforce over SSL

Scripts written with P4Python use any existing **P4TRUST** file present in their operating environment (by default, **.p4trust** in the home directory of the user that runs the script).

If the fingerprint returned by the server fails to match the one installed in the **P4TRUST** file associated with the script's run-time environment, your script will (and should!) fail to connect to the server.

Changing your password

You can use P4Python to change your password, as shown in the following example:

```
from P4 import P4

p4 = P4()
p4.user = "bruno"
p4.password = "MyOldPassword"
p4.connect()

p4.run_password( "MyOldPassword", MyNewPassword" )

# p4.password is automatically updated with the encoded password
```

Timestamp conversion

Timestamp information in P4Python is normally represented as seconds since Epoch (with the exception of **P4.Revision**). To convert this data to a more useful format, use the following procedure:

```
import datetime

...

myDate = datetime.datetime.utcfromtimestamp( int( timestampValue ) )
```

Working with comments in specs

As of P4Python 2012.3, comments in specs are preserved in the `parse_<spectype>()` and `format_<spectype>()` methods. This behavior can be circumvented by using `parse_spec( '<spectype>', spec )` and `format_spec( '<spectype>', spec )` instead of `parse_<spectype>( spec )` and `format_<spectype>( spec )`. For example:

```
p4 = P4()
p4.connect()

...

# fetch a client spec in raw format, no formatting:
specform = p4.run( 'client', '-o', tagged=False )[0]

# convert the raw document into a spec
client1 = p4.parse_client( specform )

# comments are preserved in the spec as well
print( client1.comment )

# comments can be updated
client1.comment += "# ... and now for something completely different"

# the comment is prepended to the spec ready to be sent to the user
formatted1 = p4.format_client( client1 )

# or you can strip the comments
client2 = p4.parse_spec( 'client', specform )
formatted2 = p4.format_spec( 'client', specform )
```

P4Python Classes

The P4 module consists of several public classes:

- [“P4” on page 90](#)
- [“P4.P4Exception” on page 93](#)
- [“P4.DepotFile” on page 93](#)
- [“P4.Revision” on page 94](#)
- [“P4.Integration” on page 94](#)
- [“P4.Map” on page 94](#)
- [“P4.MergeData” on page 95](#)
- [“P4.Message” on page 96](#)
- [“P4.OutputHandler” on page 96](#)
- [“P4.Progress” on page 96](#)

- [“P4.Spec” on page 97](#)

The following tables provide more details about each public class.

P4

Perforce client class. Handles connection and interaction with the Perforce server. There is one instance of each connection.

The following table lists attributes of the class **P4** in P4Python. The attributes are readable and writable unless indicated otherwise. The attributes can be strings, objects, or integers.

Attribute	Description
api_level	API compatibility level. (Lock server output to a specified server level.)
charset	Charset for Unicode servers.
client	P4CLIENT , the name of the client workspace to use.
cwd	Current working directory.
disable_tmp_cleanup	Disable cleanup of temporary objects.
encoding	Encoding to use when receiving strings from a non-Unicode server. If unset, use UTF8. Can be set to a legal Python encoding, or to raw to receive Python bytes instead of Unicode strings. Requires Python 3.
errors	An array containing the error messages received during execution of the last command.
exception_level	The exception level of the P4 instance. Values can be: • 0 : no exceptions are raised. • 1 : only errors are raised as exceptions. • 2 : warnings are also raised as exceptions. The default value is 2.
handler	An output handler.
host	P4HOST , the name of the host used.
ignore_file	The path of the ignore file, P4IGNORE .
input	Input for the next command. Can be a string, a list or a dictionary.
maxlocktime	MaxLockTime used for all following commands
maxresults	MaxResults used for all following commands

Attribute	Description
<code>maxscanrows</code>	MaxScanRows used for all following commands.
<code>messages</code>	An array of <code>P4.Message</code> objects, one for each message sent by the server.
<code>p4config_file</code>	The location of the configuration file used (<code>P4CONFIG</code>). This attribute is read-only.
<code>password</code>	<code>P4PASSWD</code> , the password used.
<code>port</code>	<code>P4PORT</code> , the port used for the connection.
<code>prog</code>	The name of the script.
<code>progress</code>	A progress indicator.
<code>server_case_insensitiv</code>	Detect whether or not the server is case sensitive.
<code>server_level</code>	Returns the current Perforce server level.
<code>server_unicode</code>	Detect whether or not the server is in Unicode mode.
<code>streams</code>	To disable streams support, set the value to <code>0</code> or <code>False</code> . By default, streams output is enabled for servers at 2011.1 or higher.
<code>tagged</code>	To disable tagged output for the following commands, set the value to <code>0</code> or <code>False</code> . By default, tagged output is enabled.
<code>track</code>	To enable performance tracking for the current connection, set the value to <code>1</code> or <code>True</code> . By default, server tracking is disabled.
<code>track_output</code>	If performance tracking is enabled, returns an array containing performance tracking information received during execution of the last command.
<code>ticket_file</code>	<code>P4TICKETS</code> , the ticket file location used.
<code>user</code>	<code>P4USER</code> , the user under which the connection is run.
<code>version</code>	The version of the script.
<code>warnings</code>	An array containing the warning messages received during execution of the last command.

The following table lists all public methods of the class `P4`. Many methods are wrappers around `P4.run()`, which sends a command to the Perforce server. Such methods are provided for your convenience.

Method	Description
<code>at_exception_level()</code>	In the context of a <code>with</code> statement, temporarily set the exception level for the duration of a block.
<code>clone()</code>	Clones from another Perforce service into a local Perforce service, and returns a new P4 object.
<code>connect()</code>	Connects to the Perforce server.
<code>connected()</code>	Returns True if connected and the connection is alive, otherwise False .
<code>delete_<spectype>()</code>	Deletes the spec <i><spectype></i> . Equivalent to: <pre>P4.run("<spectype>", "-d")</pre>
<code>disconnect()</code>	Disconnects from the Perforce server.
<code>env()</code>	Get the value of a Perforce environment variable, taking into account P4CONFIG files and (on Windows or OS X) the registry or user preferences.
<code>fetch_<spectype>()</code>	Fetches the spec <i><spectype></i> . Equivalent to: <pre>P4.run("<spectype>", "-o")</pre>
<code>format_<spectype>()</code>	Converts the spec <i><spectype></i> into a string.
<code>identify()</code>	Returns a string identifying the P4Python module.
<code>init()</code>	Initializes a new personal (local) Perforce server, and returns a new P4 object.
<code>is_ignored()</code>	Determines whether a particular file is ignored via the P4IGNORE feature.
<code>iterate_<spectype>()</code>	Iterate through specs of form <i><spectype></i> .
<code>P4()</code>	Returns a new P4 object.
<code>parse_<spectype>()</code>	Parses a string representation of the spec <i><spectype></i> and returns a dictionary.
<code>run()</code>	Runs a command on the server. Needs to be connected, or an exception is raised.
<code>run_cmd()</code>	Runs the command <i>cmd</i> . Equivalent to: <pre>P4.run("command")</pre>

Method	Description
<code>run_filelog()</code>	This command returns a list of <code>P4.DpotFile</code> objects. Specialization for the <code>P4.run()</code> method.
<code>run_login()</code>	Logs in using the specified password or ticket.
<code>run_password()</code>	Convenience method: updates the password. Takes two arguments: <i>oldpassword</i> , <i>newpassword</i>
<code>run_resolve()</code>	Interface to <code>p4 resolve</code> .
<code>run_submit()</code>	Convenience method for submitting changelists. When invoked with a change spec, it submits the spec. Equivalent to: <pre>p4.input = myspecp4.run("submit", "-i")</pre>
<code>run_tickets()</code>	Interface to <code>p4 tickets</code> .
<code>save_<spectype>()</code>	Saves the spec <i><spectype></i> . Equivalent to: <pre>P4.run("<spectype>", "-i")</pre>
<code>set_env()</code>	On Windows or OS X, set a variable in the registry or user preferences.
<code>temp_client()</code>	Creates a temporary client.
<code>while_tagged()</code>	In the context of a <code>with</code> statement, temporarily toggle tagged behavior for the duration of a block.

P4.P4Exception

Exception class. Instances of this class are raised when errors and/or (depending on the `exception_level` setting) warnings are returned by the server. The exception contains the errors in the form of a string. `P4Exception` is a subclass of the standard Python `Exception` class.

P4.DpotFile

Container class returned by `P4.run_filelog()`. Contains the name of the depot file and a list of `P4.Revision` objects.

Attribute	Description
<code>depotFile</code>	Name of the depot file.
<code>revisions</code>	List of <code>P4.Revision</code> objects

P4.Revision

Container class containing one revision of a **P4.DpotFile** object.

Attribute	Description
<u>action</u>	Action that created the revision.
<u>change</u>	Changelist number
<u>client</u>	Client workspace used to create this revision.
<u>desc</u>	Short change list description.
<u>depotFile</u>	The name of the file in the depot.
<u>digest</u>	MD5 digest of the revision.
<u>fileSize</u>	File size of this revision.
<u>integrations</u>	List of P4.Integration objects.
<u>rev</u>	Revision.
<u>time</u>	Timestamp (as <code>datetime.datetime</code> object)
<u>type</u>	File type.
<u>user</u>	User that created this revision.

P4.Integration

Container class containing one integration for a **P4.Revision** object.

Attribute	Description
<u>how</u>	Integration method (merge/branch/copy/ignored).
<u>file</u>	Integrated file.
<u>srev</u>	Start revision.
<u>erev</u>	End revision.

P4.Map

A class that allows users to create and work with Perforce mappings without requiring a connection to the Perforce server.

Method	Description
<code>P4.Map()</code>	Construct a new Map object (class method).
<code>join()</code>	Joins two maps to create a third (class method).
<code>clear()</code>	Empties a map.
<code>count()</code>	Returns the number of entries in a map.
<code>is_empty()</code>	Tests whether or not a map object is empty.
<code>insert()</code>	Inserts an entry into the map.
<code>translate()</code>	Translate a string through a map.
<code>includes()</code>	Tests whether a path is mapped.
<code>reverse()</code>	Returns a new mapping with the left and right sides reversed.
<code>lhs()</code>	Returns the left side as an array.
<code>rhs()</code>	Returns the right side as an array.
<code>as_array()</code>	Returns the map as an array

P4.MergeData

Class encapsulating the context of an individual merge during execution of a **p4 resolve** command. Passed to `P4.run_resolve()`.

Attribute	Description
<code>your_name</code>	Returns the name of "your" file in the merge. (file in workspace)
<code>their_name</code>	Returns the name of "their" file in the merge. (file in the depot)
<code>base_name</code>	Returns the name of "base" file in the merge. (file in the depot)
<code>your_path</code>	Returns the path of "your" file in the merge. (file in workspace)
<code>their_path</code>	Returns the path of "their" file in the merge. (temporary file on workstation into which their_name has been loaded)
<code>base_path</code>	Returns the path of the base file in the merge. (temporary file on workstation into which base_name has been loaded)
<code>result_path</code>	Returns the path to the merge result. (temporary file on workstation into which the automatic merge performed by the server has been loaded)
<code>merge_hint</code>	Returns hint from server as to how user might best resolve merge.

The `P4.MergeData` class also has one method:

[`run\_merge\(\)`](#)

If the environment variable `P4MERGE` is defined, run it and return a boolean based on the return value of that program.

P4.Message

Class for handling error messages in Perforce.

Method	Description
<code>severity</code>	Returns the severity of the message.
<code>generic</code>	Returns the generic class of the error.
<code>msgid</code>	Returns the unique ID of the error message.

P4.OutputHandler

Handler class that provides access to streaming output from the server; set `P4.handler` to an instance of a subclass of `P4.OutputHandler` to enable callbacks:

Method	Description
<code>outputBinary</code>	Process binary data.
<code>outputInfo</code>	Process tabular data.
<code>outputMessage</code>	Process information or errors.
<code>outputStat</code>	Process tagged output.
<code>outputText</code>	Process text data.

P4.Progress

Handler class that provides access to progress indicators from the server; set `P4.progress` to an instance of a subclass of `P4.Progress` to enable callbacks:

Method	Description
<code>init()</code>	Initialize progress indicator as designated type.
<code>setTotal()</code>	Total number of units (if known).
<code>setDescription()</code>	Description and type of units to be used for progress reporting.
<code>update()</code>	If non-zero, user has requested a cancellation of the operation.

Method	Description
<code>done()</code>	If non-zero, operation has failed.

P4.Resolver

Class for handling resolves in Perforce.

Method	Description
<code>resolve()</code>	Perform a resolve and return the resolve decision as a string.

P4.Spec

Class allowing access to the fields in a Perforce specification form.

Attribute	Description
<code>__fieldname</code>	Value associated with the field named <i>fieldname</i> .
<code>comments</code>	Array containing comments in a spec object.
<code>permitted_fields</code>	Array containing the names of the fields that are valid for this spec object.

Class P4

Description

Main interface to the Python client API.

This module provides an object-oriented interface to the Perforce version management system. Data is returned in Python arrays and dictionaries (hashes) and input can also be supplied in these formats.

Each **P4** object represents a connection to the Perforce server, and multiple commands may be executed (serially) over a single connection (which of itself can result in substantially improved performance if executing long sequences of Perforce commands).

1. Instantiate your **P4** object.
2. Specify your Perforce client environment:
 - `client`
 - `host`
 - `password`
 - `port`
 - `user`
3. Set any options to control output or error handling:
 - `exception_level`
4. Connect to the Perforce service.

The Perforce protocol is not designed to support multiple concurrent queries over the same connection. Multithreaded applications that use the C++ API or derived APIs (including P4Python) should ensure that a separate connection is used for each thread, or that only one thread may use a shared connection at a time.

5. Run your Perforce commands.
6. Disconnect from the Perforce service.

Instance Attributes

p4.api_level -> int

Contains the API compatibility level desired. This is useful when writing scripts using Perforce commands that do not yet support tagged output. In these cases, upgrading to a later server that supports tagged output for the commands in question can break your script. Using this method

allows you to lock your script to the output format of an older Perforce release and facilitate seamless upgrades. Must be called before calling `P4.connect()`.

```
from P4 import P4
p4 = P4()
p4.api_level = 67 # Lock to 2010.1 format
p4.connect()
...
p4.disconnect
```

For the API integer levels that correspond to each Perforce release, see:

<http://kb.perforce.com/article/512>

p4.charset -> string

Contains the character set to use when connect to a Unicode enabled server. Do not use when working with non-Unicode-enabled servers. By default, the character set is the value of the `P4CHARSET` environment variable. If the character set is invalid, this method raises a `P4Exception`.

```
from P4 import P4
p4 = P4()
p4.client = "www"
p4.charset = "iso8859-1"
p4.connect()
p4.run_sync()
p4.disconnect()
```

p4.client -> string

Contains the name of your client workspace. By default, this is the value of the `P4CLIENT` taken from any `P4CONFIG` file present, or from the environment according to the normal Perforce conventions.

p4.cwd -> string

Contains the current working directory. Can be called prior to executing any Perforce command. Sometimes necessary if your script executes a `chdir()` as part of its processing.

```
from P4 import P4
p4 = P4()
p4.cwd = "/home/bruno"
```

p4.disable_tmp_cleanup -> string

Invoke this prior to connecting if you need to use multiple `P4` connections in parallel in a multi-threaded Python application.

```
from P4 import P4
p4 = P4()
p4.disable_tmp_cleanup()
p4.connect()
...
p4.disconnect()
```

p4.encoding -> string

When decoding strings from a non-Unicode server, strings are assumed to be encoded in UTF8. To use another encoding, set **p4.encoding** to a legal Python encoding, or **raw** to receive Python bytes instead of a Unicode string. Available only when compiled with Python 3.

p4.errors -> list (read-only)

Returns an array containing the error messages received during execution of the last command.

```
from P4 import P4, P4Exception
p4 = P4()

try:
    p4.connect()
    p4.exception_level = 1
    # ignore "File(s) up-to-date"s
    files = p4.run_sync()

except P4Exception:
    for e in p4.errors:
        print e

finally:
    p4.disconnect()
```

p4.exception_level -> int

Configures the events which give rise to exceptions. The following three levels are supported:

- **0** : disables all exception handling and makes the interface completely procedural; you are responsible for checking the **p4.errors** and **p4.warnings** arrays.
- **1** : causes exceptions to be raised only when errors are encountered.
- **2** : causes exceptions to be raised for both errors and warnings. This is the default.

For example:

```
from P4 import P4
p4 = P4()
p4.exception_level = 1
p4.connect() # P4Exception on failure
p4.run_sync() # File(s) up-to-date is a warning - no exception raised
p4.disconnect()
```

p4.handler -> handler

Set the output handler to a subclass of **P4.OutputHandler**.

p4.host -> string

Contains the name of the current host. It defaults to the value of **P4HOST** taken from any **P4CONFIG** file present, or from the environment as per the usual Perforce convention. Must be called before connecting to the Perforce server.

```
from P4 import P4
p4 = P4()
p4.host = "workstation123.perforce.com"
p4.connect()
...
p4.disconnect()
```

p4.ignore_file -> string

Contains the path of the ignore file. It defaults to the value of **P4IGNORE**. Set **P4.ignore_file** prior to calling **P4.is_ignored()**.

```
from P4 import P4
p4 = P4()
p4.connect()
p4.ignore_file = "/home/bruno/workspace/.ignore"
p4.disconnect()
```

p4.input -> string | dict | list

Contains input for the next command.

Set this attribute prior to running a command that requires input from the user. When the command requests input, the specified data is supplied to the command. Typically, commands of the form **p4 cmd -i** are invoked using the **P4.save_<spectype>()** methods, which retrieve the value from **p4.input** internally; there is no need to set **p4.input** when using the **P4.save_<spectype>()** shortcuts.

You may pass a string, a hash, or (for commands that take multiple inputs from the user) an array of strings or hashes. If you pass an array, note that the first element of the array will be popped each time Perforce asks the user for input.

For example, the following code supplies a description for the default changelist and then submits it to the depot:

```
from P4 import P4
p4 = P4()
p4.connect()
change = p4.run_change( "-o" )[0]
change[ "Description" ] = "Autosubmitted changelist"
p4.input = change
p4.run_submit( "-i" )
p4.disconnect()
```

p4.iterate_<spectype>(arguments) -> P4.Spec

The `iterate_<spectype>()` methods are shortcut methods that allow you to quickly iterate through clients, labels, branches, etc. Valid *<spectypes>* are **clients**, **labels**, **branches**, **changes**, **streams**, **jobs**, **users**, **groups**, **depots** and **servers**. Valid arguments are any arguments that would be valid for the corresponding `run_<spectype>()` command.

For example:

```
for client in p4.iterate_clients():
    # do something with the client spec
```

is equivalent to:

```
for c in p4.run_clients():
    client = p4.fetch_client( c['client'] )
```

p4.maxlocktime -> int

Limit the amount of time (in milliseconds) spent during data scans to prevent the server from locking tables for too long. Commands that take longer than the limit will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxlocktime` for information on the commands that support this limit.

p4.maxresults -> int

Limit the number of results Perforce permits for subsequent commands. Commands that produce more than this number of results will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxresults` for information on the commands that support this limit.

p4.maxscanrows -> int

Limit the number of database records Perforce scans for subsequent commands. Commands that attempt to scan more than this number of records will be aborted. The limit remains in force until you

disable it by setting it to zero. See `p4 help maxscanrows` for information on the commands that support this limit.

p4.messages -> list (read-only)

Returns a list of `P4.Message` objects, one for each message (info, warning or error) sent by the server.

p4.p4config_file -> string (read-only)

Contains the name of the current `P4CONFIG` file, if any. This attribute cannot be set.

p4.password -> string

Contains your Perforce password or login ticket. If not used, takes the value of `P4PASSWD` from any `P4CONFIG` file in effect, or from the environment according to the normal Perforce conventions.

This password is also used if you later call `p4.run_login()` to log in using the 2003.2 and later ticket system. After running `p4.run_login()`, the attribute contains the ticket allocated by the server.

```
from P4 import P4
p4 = P4()
p4.password = "mypass"
p4.connect()
p4.run_login()
```

p4.port -> string

Contains the host and port of the Perforce server to which you want to connect. It defaults to the value of `P4PORT` in any `P4CONFIG` file in effect, and then to the value of `P4PORT` taken from the environment.

```
from P4 import P4
p4 = P4()
p4.port = "localhost:1666"
p4.connect()
...
```

p4.prog -> string

Contains the name of the program, as reported to Perforce system administrators running `p4 monitor show -e`. The default is unnamed `p4-python script`.

```
from P4 import P4
p4 = P4()
p4.prog = "sync-script"
puts( p4.prog )
p4.connect
...
```

p4.progress -> progress

Set the progress indicator to a subclass of **P4.Progress**.

p4.server_case_insensitive -> boolean

Detects whether or not the server is case-sensitive.

p4.server_level -> int (read-only)

Returns the current Perforce server level. Each iteration of the Perforce server is given a level number. As part of the initial communication this value is passed between the client application and the Perforce server. This value is used to determine the communication that the Perforce server will understand. All subsequent requests can therefore be tailored to meet the requirements of this server level.

This attribute is 0 before the first command is run, and is set automatically after the first communication with the server.

For the API integer levels that correspond to each Perforce release, see:

<http://kb.perforce.com/article/571>

p4.server_unicode -> boolean

Detects whether or not the server is in Unicode mode.

p4.streams -> int

If 1 or True, **p4.streams** enables support for streams. By default, streams support is enabled at 2011.1 or higher (**api_level** >= 70). Raises a **P4Exception** if you attempt to enable streams on a pre-2011.1 server. You can enable or disable support for streams both before and after connecting to the server.

```
from P4 import P4
p4 = P4()
p4.streams = False
print p4.streams
```

p4.tagged -> int

If 1 or True, **p4.tagged** enables tagged output. By default, tagged output is on.

```
from P4 import P4
p4 = P4()
p4.tagged = False
print p4.tagged
```

p4.ticket_file -> string

Contains the location of the P4TICKETS file.

p4.track -> boolean

If set to 1 or True, **p4.track** indicates that server performance tracking is enabled for this connection. By default, performance tracking is disabled.

p4.track_output -> list (read-only)

If performance tracking is enabled with [p4.track](#), returns an array containing the performance data received during execution of the last command.

```
from P4 import P4
p4 = P4()
p4.track = 1
p4.run_info()
print p4.track_output
```

p4.user -> string

Contains the Perforce username. It defaults to the value of P4USER taken from any P4CONFIG file present, or from the environment as per the usual Perforce convention.

```
from P4 import P4
p4 = P4()
p4.user = "bruno"
p4.connect()
...
p4.disconnect()
```

p4.version -> string

Contains the version of the program, as reported to Perforce system administrators in the server log.

```
from P4 import P4
p4 = P4()
p4.version = "123"
puts( p4.version )
p4.connect()
...
p4.disconnect()
```

p4.warnings -> list (read-only)

Contains the array of warnings that arose during execution of the last command.

```
from P4 import P4, P4Exception
p4 = P4()

try:
    p4.connect()
    p4.exception_level = 2 # File(s) up-to-date is a warning
    files = p4.run_sync()

except P4Exception, ex:
    for w in p4.warnings:
        print w

finally:
    p4.disconnect()
```

Class Methods

P4.P4()

Construct a new **P4** object. For example:

```
from P4 import P4
P4.P4()
```

P4.clone(arguments...)

Clone from another Perforce service into a local Perforce server, and returns a new **P4** object.

P4.clone() requires specification of the port of the source Perforce service from which files and version history should be cloned from, and either a *remotespec* or a *filespec* that specify which files and history to clone. For example, to clone using a *remotespec*:

```
import P4
p4 = P4.clone( "-p", "port", "-r", "remotespec" )
```

or to clone using a *filespec*:

```
import P4
p4 = P4.clone( "-p", "port", "-f", "filespec" )
```

The cloned instance inherits the case sensitivity and Unicode settings from the source Perforce service.

Note

All of the additional DVCS commands, such as **p4 push** or **p4 switch**, are available automatically in the usual fashion. For example: **p4.run_push()**. See [“p4.run_<cmd>\(\)” on page 113](#) for details.

P4.identify()

Return the version of P4Python that you are using.

```
python -c "from P4 import P4; print P4.identify()"
```

The read-only string attributes `PATCHLEVEL` and `OS` are also available to test an installation of P4Python without having to parse the output of `P4.identify()`.

If applicable, `P4.identify()` also reports the version of the OpenSSL library used for building the underlying Perforce C++ API with which P4Python was built.

P4.init([arguments])

Initializes a new, personal (local) Perforce server, and returns a new `P4` object.

Without any arguments, `P4.init()` creates a new DVCS server in the current working directory, using the settings for case sensitivity and Unicode support from current environment variables.

`P4.init()` accepts the following keyword arguments:

Keyword	Explanation	Example
<code>client</code>	Workspace and server name	<code>client="sknop-dvcs"</code>
<code>user</code>	Perforce username used for pushing	<code>user="sven_erik_knop"</code>
<code>directory</code>	local path of the root directory for the new server	<code>directory="/tmp/test-dvcs"</code>
<code>casesensitive</code>	specify case sensitivity	<code>casesensitive=False</code>
<code>unicode</code>	specify whether Unicode is enabled	<code>unicode=True</code>

```
import P4
p4 = P4.init( directory="/Users/sknop/dvcs/" )
p4.connect()
# ...
p4.disconnect()
```

The `P4` instance returned by `P4.init()` has the port, user, and client workspace already set; all that is required for you is to connect to the server to perform any commands. Connection is not automatic, to give you an opportunity to set any protocol parameters; these parameters can only be set once before a connection is established.

Note

All of the additional DVCS commands, such as `p4 push` or `p4 switch`, are available automatically in the usual fashion. For example: `p4.run_push()`. See [“p4.run_<cmd>\(\)” on page 113](#) for details.

Instance Methods

p4.at_exception_level()

In the context of a **with** statement, temporarily set the exception level for a block. For example:

```
from P4 import P4
p4 = P4()
p4.connect()
with p4.at_exception_level( P4.RAISE_ERRORS ):
    # no exceptions for warnings
    p4.run_sync( "//depot/main/..." )

# exceptions back to normal...
```

p4.connect()

Initializes the Perforce client and connects to the server.

If the connection is successfully established, returns **None**. If the connection fails and **P4.exception_level** is 0, returns False, otherwise raises a **P4Exception**. If already connected, prints a message.

```
from P4 import P4
p4 = P4()
p4.connect()
...
p4.disconnect()
```

P4.connect() returns a context management object that is usable with a **with** statement within a block; after the block is finished, the connection is automatically disconnected:

```
import P4
p4 = P4.P4()
with p4.connect():
    # block in context of connection
    ...

# p4 is disconnected outside the block
...
```

p4.connected() -> boolean

Returns **true** if connected to the Perforce server and the connection is alive, otherwise **false**.

```
from P4 import P4
p4 = P4()

print p4.connected()
p4.connect()
print p4.connected()
```

p4.delete_<spectype>([options], name) -> list

The `delete_<spectype>()` methods are shortcut methods that allow you to delete the definitions of clients, labels, branches, etc. These methods are equivalent to:

```
p4.run( "<spectype>", '-d', [options], "spec name" )
```

The following code uses `P4.delete_client()` to delete client workspaces that have not been accessed in more than 365 days:

```
from P4 import P4, P4Exception
from datetime import datetime, timedelta

now = datetime.now()
p4 = P4()

try:
    p4.connect()
    for client in p4.run_clients():
        atime = datetime.utcfromtimestamp( int( client[ "Access" ] ) )
        # If the client has not been accessed for a year, delete it
        if ( atime + timedelta( 365 ) ) < now :
            p4.delete_client( '-f', client[ "client" ] )

except P4Exception:
    for e in p4.errors:
        print e

finally:
    p4.disconnect()
```

p4.disconnect()

Disconnect from the Perforce server. Call this method before exiting your script.

```
from P4 import P4
p4 = P4()

p4.connect()
...
p4.disconnect()
```

p4.env(var)

Get the value of a Perforce environment variable, taking into account **P4CONFIG** files and (on Windows or OS X) the registry or user preferences.

```
from P4 import P4
p4 = P4()

print p4.env( "P4PORT" )
```

p4.fetch_<spectype>() -> P4.Spec

The `fetch_<spectype>()` methods are shortcuts for running `p4.run( "<spectype>", "-o" ).pop( 0 )`. For example:

```
label      = p4.fetch_label( "labelname" )
change     = p4.fetch_change( changeno )
clientspec = p4.fetch_client( "clientname" )
```

are equivalent to:

```
label      = p4.run( "label", "-o", "labelname" )[0]
change     = p4.run( "change", "-o", changeno )[0]
clientspec = p4.run( "client", "-o", "clientname" )[0]
```

p4.format_spec("<spectype>", dict) -> string

Converts the fields in the dict containing the elements of a Perforce form (spec) into the string representation familiar to users. The first argument is the type of spec to format: for example, client, branch, label, and so on. The second argument is the hash to parse.

There are shortcuts available for this method. You can use `p4.format_<spectype>( dict )` instead of `p4.format_spec( "<spectype>", dict )`, where `<spectype>` is the name of a Perforce spec, such as client, label, etc.

p4.format_<spectype>(dict) -> string

The `format_<spectype>()` methods are shortcut methods that allow you to quickly fetch the definitions of clients, labels, branches, etc. They're equivalent to:

```
p4.format_spec( "<spectype>", dict )
```

p4.is_ignored("<path>") -> boolean

Returns `true` if the `<path>` is ignored via the **P4IGNORE** feature. The `<path>` can be a local relative or absolute path.

```
from P4 import P4
p4 = P4()

p4.connect()
if ( p4.is_ignored( "/home/bruno/workspace/file.txt" )):
    print "Ignored."
else:
    print "Not ignored."

p4.disconnect()
```

p4.parse_spec("<spectype>", string) -> P4.Spec

Parses a Perforce form (spec) in text form into a Python dict using the spec definition obtained from the server. The first argument is the type of spec to parse: **client**, **branch**, **label**, and so on. The second argument is the string buffer to parse.

There are shortcuts available for this method. You can use:

```
p4.parse_<spectype>( buf )
```

instead of:

```
p4.parse_spec( "<spectype>", buf )
```

where *<spectype>* is one of **client**, **branch**, **label**, and so on.

p4.parse_<spectype>(string) -> P4.Spec

This is equivalent to:

```
p4.parse_spec( "<spectype>", string )
```

For example, `parse_job( myJob )` converts the String representation of a job spec into a Spec object.

To parse a spec, **P4** needs to have the spec available. When not connected to the Perforce server, **P4** assumes the default format for the spec, which is hardcoded. This assumption can fail for jobs if the server's jobspec has been modified. In this case, your script can load a job from the server first with the command `p4.fetch_job( 'somename' )`, and **P4** will cache and use the spec format in subsequent `p4.parse_job()` calls.

p4.run("<cmd>", [arg, ...])

Base interface to all the run methods in this API. Runs the specified Perforce command with the arguments supplied. Arguments may be in any form as long as they can be converted to strings by `str()`.

The `p4.run()` method returns a list of results whether the command succeeds or fails; the list may, however, be empty. Whether the elements of the array are strings or dictionaries depends on:

- i. server support for tagged output for the command, and
- ii. whether tagged output was disabled by calling `p4.tagged = False`.

In the event of errors or warnings, and depending on the exception level in force at the time, `p4.run()` raises a `P4Exception`. If the current exception level is below the threshold for the error/warning, `p4.run()` returns the output as normal and the caller must explicitly review `p4.errors` and `p4.warnings` to check for errors or warnings.

```
from P4 import P4
p4 = P4()
p4.connect()
spec = p4.run( "client", "-o" )[0]
p4.disconnect()
```

Shortcuts are available for `p4.run()`. For example:

```
p4.run_command( args )
```

is equivalent to:

```
p4.run( "command", args )
```

There are also some shortcuts for common commands such as editing Perforce forms and submitting. For example, this:

```
from P4 import P4
p4 = P4()
p4.connect()
clientspec = p4.run_client( "-o" ).pop( 0 )
clientspec[ "Description" ] = "Build client"
p4.input = clientspec
p4.run_client( "-i" )
p4.disconnect()
```

...may be shortened to:

```
from P4 import P4
p4 = P4()
p4.connect()
clientspec = p4.fetch_client()
clientspec[ "Description" ] = "Build client"
p4.save_client( clientspec )
p4.disconnect()
```

The following are equivalent:

Shortcut	Equivalent to
<code>p4.delete_<spectype>()</code>	<code>p4.run("<spectype>", "-d ")</code>
<code>p4.fetch_<spectype>()</code>	<code>p4.run("<spectype>", "-o ").shift</code>
<code>p4.save_<spectype>(spec)</code>	<code>p4.input = spec</code> <code>p4.run("<spectype>", "-i")</code>

As the commands associated with `p4.fetch_<spectype>()` typically return only one item, these methods do not return an array, but instead return the first result element.

For convenience in submitting changelists, changes returned by `p4.fetch_change()` can be passed to `p4.run_submit()`. For example:

```
from P4 import P4
p4 = P4()
p4.connect()

spec = p4.fetch_change()
spec[ "Description" ] = "Automated change"
p4.run_submit( spec )
p4.disconnect()
```

p4.run_<cmd>()

Shorthand for:

```
p4.run( "<cmd>", arguments... )
```

p4.run_filelog(<fileSpec>) -> list

Runs a `p4 filelog` on the *fileSpec* provided and returns an array of `P4.DepotFile` results (when executed in tagged mode), or an array of strings when executed in nontagged mode. By default, the raw output of `p4 filelog` is tagged; this method restructures the output into a more user-friendly (and object-oriented) form.

For example:

```
from P4 import P4, P4Exception
p4 = P4()

try:
    p4.connect()
    for r in p4.run_filelog( "index.html" )[0].revisions:
        for i in r.integrations:
            # Do something

except P4Exception:
    for e in p4.errors:
        print e

finally:
    p4.disconnect()
```

p4.run_login(<arg>...) -> list

Runs **p4 login** using a password or ticket set by the user.

p4.run_password(oldpass, newpass) -> list

A thin wrapper to make it easy to change your password. This method is (literally) equivalent to the following:

```
p4.input( [ oldpass, newpass, newpass ] )
p4.run( "password" )
```

For example:

```
from P4 import P4, P4Exception
p4 = P4()
p4.password = "myoldpass"

try:
    p4.connect()
    p4.run_password( "myoldpass", "mynewpass" )

except P4Exception:
    for e in p4.errors:
        print e

finally:
    p4.disconnect()
```

p4.run_resolve([<resolver>], [arg...]) -> list

Run a **p4 resolve** command. Interactive resolves require the *<resolver>* parameter to be an object of a class derived from **P4.Resolver**. In these cases, the **P4.Resolver.resolve()** method is called to handle the resolve. For example:

```
p4.run_resolve ( resolver=MyResolver() )
```

To perform an automated merge that skips whenever conflicts are detected:

```
class MyResolver( P4.Resolver ):
    def resolve( self, mergeData ):
        if not mergeData.merge_hint == "e":
            return mergeData.merge_hint
        else:
            return "s" # skip the resolve, there is a conflict
```

In non-interactive resolves, no `P4.Resolver` object is required. For example:

```
p4.run_resolve ( "-at" )
```

p4.run_submit([hash], [arg...]) -> list

Submit a changelist to the server. To submit a changelist, set the fields of the changelist as required and supply any flags:

```
change = p4.fetch_change()
change._description = "Some description"
p4.run_submit( "-r", change )
```

You can also submit a changelist by supplying the arguments as you would on the command line:

```
p4.run_submit( "-d", "Some description", "somedir/..." )
```

p4.run_tickets() -> list

`p4.run_tickets()` returns an array of lists of the form (`p4port`, `user`, `ticket`) based on the contents of the local tickets file.

p4.save_<spectype>()>

The `save_<spectype>()` methods are shortcut methods that allow you to quickly update the definitions of clients, labels, branches, etc. They are equivalent to:

```
p4.input = dictOrString
p4.run( "<spectype>", "-i" )
```

For example:

```
from P4 import P4, P4Exception
p4 = P4()

try:
    p4.connect()
    client = p4.fetch_client()
    client[ "Owner" ] = p4.user
    p4.save_client( client )

except P4Exception:
    for e in p4.errors:
        print e

finally:
    p4.disconnect()
```

p4.set_env(var, value)

On Windows or OS X, set a variable in the registry or user preferences. To unset a variable, pass an empty string as the second argument. On other platforms, an exception is raised.

```
p4.set_env = ( "P4CLIENT", "my_workspace" )
p4.set_env = ( "P4CLIENT", "" )
```

p4.temp_client("<prefix>", "<template>")

Creates a temporary client, using the prefix *<prefix>* and based upon a client template named *<template>*, then switches `P4.client` to the new client, and provides a temporary root directory. The prefix makes is easy to exclude the workspace from the spec depot.

This is intended to be used with a `with` statement within a block; after the block is finished, the temp client is automatically deleted and the temporary root is removed.

For example:

```
from P4 import P4
p4 = P4()
p4.connect()
with p4.temp_client( "temp", "my_template" ) as t:
    p4.run_sync()
    p4.run_edit( "foo" )
    p4.run_submit( "-dcomment" )
```

p4.while_tagged(boolean)

In the context of a `with` statement, enable or disable tagged behavior for the duration of a block. For example:

```
from P4 import P4
p4 = P4()
p4.connect()
with p4.while_tagged( False ):
    # tagged output disabled for this block
    print p4.run_info()

# tagged output back to normal
...
```

Class P4.P4Exception

Description

Instances of this class are raised when **P4** encounters an error or a warning from the server. The exception contains the errors in the form of a string. **P4Exception** is a shallow subclass of the standard Python Exception class.

Class Attributes

None.

Class Methods

None.

Class P4.DpotFile

Description

Utility class providing easy access to the attributes of a file in a Perforce depot. Each **P4.DpotFile** object contains summary information about the file and a list of revisions (**P4.Revision** objects) of that file. Currently, only the **P4.run_filelog()** method returns a list of **P4.DpotFile** objects.

Instance Attributes

df.depotFile -> string

Returns the name of the depot file to which this object refers.

df.revisions -> list

Returns a list of **P4.Revision** objects, one for each revision of the depot file.

Class Methods

None.

Instance Methods

None.

Class P4.Revision

Description

Utility class providing easy access to the revisions of `P4.DpotFile` objects. Created by `P4.run_filelog()`.

Instance Attributes

rev.action -> string

Returns the name of the action which gave rise to this revision of the file.

rev.change -> int

Returns the change number that gave rise to this revision of the file.

rev.client -> string

Returns the name of the client from which this revision was submitted.

rev.depotFile -> string

Returns the name of the depot file to which this object refers.

rev.desc -> string

Returns the description of the change which created this revision. Note that only the first 31 characters are returned unless you use `p4 filelog -l` for the first 250 characters, or `p4 filelog -l` for the full text.

rev.digest -> string

Returns the MD5 digest of this revision.

rev.fileSize -> string

Returns this revision's size in bytes.

rev.integrations -> list

Returns the list of `P4.Integration` objects for this revision.

rev.rev -> int

Returns the number of this revision of the file.

rev.time -> datetime

Returns the date / time that this revision was created.

rev.type -> string

Returns this revision's Perforce filetype.

rev.user -> string

Returns the name of the user who created this revision.

Class Methods

None.

Instance Methods

None.

Class P4.Integration

Description

Utility class providing easy access to the details of an integration record. Created by `P4.run_filelog()`.

Instance Attributes

integ.how -> string

Returns the type of the integration record - how that record was created.

integ.file -> string

Returns the path to the file being integrated to/from.

integ.srev -> int

Returns the start revision number used for this integration.

integ.erev -> int

Returns the end revision number used for this integration.

Class Methods

None.

Instance Methods

None.

Class P4.Map

Description

The **P4.Map** class allows users to create and work with Perforce mappings, without requiring a connection to a Perforce server.

Instance Attributes

None.

Class Methods

P4.Map([list]) -> P4.Map

Constructs a new **P4.Map** object.

P4.Map.join (map1, map2) -> P4.Map

Join two **P4.Map** objects and create a third.

The new map is composed of the left-hand side of the first mapping, as joined to the right-hand side of the second mapping. For example:

```
# Map depot syntax to client syntax
client_map = P4.Map()
client_map.insert( "//depot/main/...", "//client/..." )

# Map client syntax to local syntax
client_root = P4.Map()
client_root.insert( "//client/...", "/home/bruno/workspace/..." )

# Join the previous mappings to map depot syntax to local syntax
local_map = P4.Map.join( client_map, client_root )
local_path = local_map.translate( "//depot/main/www/index.html" )

# local_path is now /home/bruno/workspace/www/index.html
```

Instance Methods

map.clear()

Empty a map.

map.count() -> int

Return the number of entries in a map.

map.is_empty() -> boolean

Test whether a map object is empty.

map.insert(string ...)

Inserts an entry into the map.

May be called with one or two arguments. If called with one argument, the string is assumed to be a string containing either a half-map, or a string containing both halves of the mapping. In this form, mappings with embedded spaces must be quoted. If called with two arguments, each argument is assumed to be half of the mapping, and quotes are optional.

```
# called with two arguments:
map.insert( "//depot/main/...", "//client/..." )

# called with one argument containing both halves of the mapping:
map.insert( "//depot/live/... //client/live/..." )

# called with one argument containing a half-map:
# This call produces the mapping "depot/... depot/..."
map.insert( "depot/..." )
```

map.translate (string, [boolean]) -> string

Translate a string through a map, and return the result. If the optional second argument is **1**, translate forward, and if it is **0**, translate in the reverse direction. By default, translation is in the forward direction.

map.includes(string) -> boolean

Tests whether a path is mapped or not.

```
if map.includes( "//depot/main/..." ):
    ...
```

map.reverse() -> P4.Map

Return a new **P4.Map** object with the left and right sides of the mapping swapped. The original object is unchanged.

map.lhs() -> list

Returns the left side of a mapping as an array.

map.rhs() -> list

Returns the right side of a mapping as an array.

map.as_array() -> list

Returns the map as an array.

Class P4.MergeData

Description

Class containing the context for an individual merge during execution of a `p4 resolve`.

Instance Attributes

md.your_name -> string

Returns the name of "your" file in the merge. This is typically a path to a file in the workspace.

md.their_name -> string

Returns the name of "their" file in the merge. This is typically a path to a file in the depot.

md.base_name -> string

Returns the name of the "base" file in the merge. This is typically a path to a file in the depot.

md.your_path -> string

Returns the path of "your" file in the merge. This is typically a path to a file in the workspace.

md.their_path -> string

Returns the path of "their" file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `their_name` have been loaded.

md.base_path -> string

Returns the path of the base file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `base_name` have been loaded.

md.result_path -> string

Returns the path to the merge result. This is typically a path to a temporary file on your local machine in which the contents of the automatic merge performed by the server have been loaded.

md.merge_hint -> string

Returns the hint from the server as to how it thinks you might best resolve this merge.

Instance Methods

md.run_merge() -> boolean

If the environment variable `P4MERGE` is defined, `md.run_merge()` invokes the specified program and returns a boolean based on the return value of that program.

Class P4.Message

Description

`P4.Message` objects contain error or other diagnostic messages from the Perforce server; they are returned in `P4.messages`.

Script writers can test the severity of the messages in order to determine if the server message consisted of command output (`E_INFO`), warnings, (`E_WARN`), or errors (`E_FAILED` / `E_FATAL`).

Class Methods

None.

Instance Attributes

`message.severity -> int`

Severity of the message, which is one of the following values:

Value	Meaning
<code>E_EMPTY</code>	No error.
<code>E_INFO</code>	Informational message only.
<code>E_WARN</code>	Warning message only.
<code>E_FAILED</code>	Command failed.
<code>E_FATAL</code>	Severe error; cannot continue.

`message.generic -> int`

Returns the generic class of the error.

`message.msgid -> int`

Returns the unique ID of the message.

Class P4.OutputHandler

Description

The `P4.OutputHandler` class is a handler class that provides access to streaming output from the server. After defining the output handler, set `p4.handler` to an instance of a subclass of `P4.OutputHandler`, use `p4.using_handler( MyHandler() )`, or pass the handler as a named parameter for one statement only.

By default, `P4.OutputHandler` returns `REPORT` for all output methods. The different return options are:

Value	Meaning
<code>REPORT</code>	Messages added to output (don't handle, don't cancel)
<code>HANDLED</code>	Output is handled by class (don't add message to output).
<code>REPORT CANCEL</code>	Operation is marked for cancel, message is added to output.
<code>HANDLED CANCEL</code>	Operation is marked for cancel, message not added to output.

Class Methods

class MyHandler(P4.OutputHandler)

Constructs a new subclass of `P4.OutputHandler`.

Instance Methods

outputBinary -> int

Process binary data.

outputInfo -> int

Process tabular data.

outputMessage -> int

Process informational or error messages.

outputStat -> int

Process tagged data.

outputText -> int

Process text data.

Class P4.Progress

Description

The **P4.Progress** class is a handler class that provides access to progress indicators from the server. After defining the progress class, set **P4.progress** to an instance of a subclass of **P4.Progress**, use **p4.using_progress(MyProgress())**, or pass the progress indicator as a named parameter for one statement only.

You must implement all five of the following methods: **init()**, **setDescription()**, **update()**, **setTotal()**, and **done()**, even if the implementation consists of trivially returning 0.

Instance Attributes

None.

Class Methods

class MyProgress(P4.Progress)

Constructs a new subclass of **P4.Progress**.

Instance Methods

progress.init() -> int

Initialize progress indicator.

progress.setDescription(string, int) -> int

Description and type of units to be used for progress reporting.

progress.update() -> int

If non-zero, user has requested a cancellation of the operation.

progress.setTotal(<total>) -> int

Total number of units expected (if known).

progress.done() -> int

If non-zero, operation has failed.

Class P4.Resolver

Description

P4.Resolver is a class for handling resolves in Perforce. It is intended to be subclassed, and for subclasses to override the `resolve()` method. When **P4.run_resolve()** is called with a **P4.Resolver** object, it calls the **P4.Resolver.resolve()** method of the object once for each scheduled resolve.

Instance Attributes

None.

Class Methods

None.

Instance Methods

resolver.resolve(self, mergeData) -> string

Returns the resolve decision as a string. The standard Perforce resolve strings apply:

String	Meaning
ay	Accept Yours.
at	Accept Theirs.
am	Accept Merge result.
ae	Accept Edited result.
s	Skip this merge.
q	Abort the merge.

By default, all automatic merges are accepted, and all merges with conflicts are skipped. The **P4.Resolver.resolve()** method is called with a single parameter, which is a reference to a **P4.MergeData** object.

Class P4.Spec

Description

Utility class providing easy access to the attributes of the fields in a Perforce form.

Only valid field names may be set in a **P4.Spec** object. Only the field name is validated, not the content. Attributes provide easy access to the fields.

Instance Attributes

spec.<fieldname> -> string

Contains the value associated with the field named *<fieldname>*.

spec.comment -> dict

Contains an array containing the comments associated with the spec object.

spec.permitted_fields -> dict

Contains an array containing the names of fields that are valid in this spec object. This does not imply that values for all of these fields are actually set in this object, merely that you may choose to set values for any of these fields if you want to.

Class Methods

P4.Spec.new(dict) -> P4.Spec

Constructs a new **P4.Spec** object given an array of valid fieldnames.

Instance Methods

None.

Introduction

P4PHP, the PHP interface to the Perforce API, enables you to write PHP code that interacts with a Perforce server. P4PHP enables your PHP scripts to:

- Get Perforce data and forms in arrays.
- Edit Perforce forms by modifying arrays.
- Provide exception-based error handling and optionally ignore warnings.
- Issue multiple commands on a single connection (performs better than spawning single commands and parsing the results).

The most recent release of P4PHP is 2013.1.

System Requirements

P4PHP is supported on Windows, Linux, FreeBSD, and OS X.

To build P4PHP from source, your development machine must also have:

- PHP 5.3.x, 5.4.x, or 5.5.x.
- The 2014.1 Perforce C/C++ API for your target platform
- The same C++ compiler used to build the Perforce C++ API on your target platform.

(If you get "unresolved symbol" errors when building or running P4PHP, you probably used the wrong compiler or the wrong Perforce API build.)

Installing P4PHP

You can download P4PHP from the Perforce web site:

<http://www.perforce.com/product/components/apis>

You must build the interface from source, as described in the release notes packaged with P4PHP.

Programming with P4PHP

The following example illustrates the basic structure of a P4PHP script. The example establishes a connection, issues a command, and tests for errors resulting from the command.

```
<?php

$p4 = new P4();
$p4->port = "1666";
$p4->user = "fred";
$p4->client = "fred-ws";

try {
    $p4->connect();
    $info = $p4->run( "info" );
    foreach ( $info[0] as $key => $val ) {
        print "$key = $val\n";
    }
    $p4->run( "edit", "file.txt" );
    $p4->disconnect();
} catch ( P4_Exception $e ) {
    print $e->getMessage() . "\n";
    foreach ( $p4->errors as $error ) {
        print "Error: $error\n";
    }
}
?>
```

This example creates a client workspace from a template and syncs it:

```
<?php

$template = "my-client-template";
$client_root = "/home/user/work/my-root";
$p4 = new P4();

try {
    $p4->connect();

    // Convert client spec into an array

    $client = $p4->fetch_client( "-t", $template );
    $client['Root'] = $client_root;
    $p4->save_client( $client );
    $p4->run_sync();

} catch ( P4_Exception $e ) {
    // If any errors occur, we'll jump in here. Just log them
    // and raise the exception up to the higher level
}
?>
```

Submitting a Changelist

This example creates a changelist, modifies it, and then submits it:

```
<?php

$p4 = new P4();
$p4->connect();

$change = $p4->fetch_change();

// Files were opened elsewhere and we want to
// submit a subset that we already know about.

$myfiles = array(
    '//depot/some/path/file1.c',
    '//depot/some/path/file1.h'
);

$change['description'] = "My changelist\nSubmitted from P4PHP\n";
$change['files'] = $myfiles;
$p4->run_submit( $change );

?>
```

Logging into Perforce using ticket-based authentication

On some servers, users might need to log in to Perforce before issuing commands. The following example illustrates login using Perforce tickets.

```
<?php

$p4 = new P4();
$p4->user = "bruno";
$p4->connect();
$p4->run_login( 'my_password' );

$opened = $p4->
run_opened();

?>
```

Connecting to Perforce over SSL

Scripts written with P4PHP use any existing **P4TRUST** file present in their operating environment (by default, **.p4trust** in the home directory of the user that runs the script).

If the fingerprint returned by the server fails to match the one installed in the **P4TRUST** file associated with the script's run-time environment, your script will (and should!) fail to connect to the server.

Changing your password

You can use P4PHP to change your password, as shown in the following example:

```

<?php

$p4 = new P4();
$p4->user = "bruno";
$p4->password = "MyOldPassword";
$p4->connect();

$p4->run_password( "MyOldPassword", "MyNewPassword" );

// $p4->password is automatically updated with the encoded password

?>

```

P4PHP Classes

The P4 module consists of several public classes:

- [“P4” on page 136](#)
- [“P4_Exception” on page 139](#)
- [“P4_DepotFile” on page 139](#)
- [“P4_Revision” on page 139](#)
- [“P4_Integration” on page 140](#)
- [“P4_Map” on page 140](#)
- [“P4_MergeData” on page 141](#)
- [“P4_OutputHandlerAbstract” on page 141](#)
- [“P4_Resolver” on page 142](#)

The following tables provide more details about each public class.

P4

Perforce client class. Handles connection and interaction with the Perforce server. There is one instance of each connection.

The following table lists properties of the class **P4** in P4PHP. The properties are readable and writable unless indicated otherwise. The properties can be strings, arrays, or integers.

Property	Description
<code>api_level</code>	API compatibility level. (Lock server output to a specified server level.)
<code>charset</code>	Charset for Unicode servers.
<code>client</code>	P4CLIENT, the name of the client workspace to use.

Property	Description
<code>cwd</code>	Current working directory.
<code>errors</code>	A read-only array containing the error messages received during execution of the last command.
<code>exception_level</code>	The exception level of the P4 instance. Values can be: • <code>0</code> : no exceptions are raised • <code>1</code> : only errors are raised as exceptions • <code>2</code> : warnings are also raised as exceptions The default value is 2.
<code>expand_sequences</code>	Control whether keys with trailing numbers are expanded into arrays; by default, true, for backward-compatibility.
<code>handler</code>	An output handler.
<code>host</code>	<code>P4HOST</code> , the name of the host used.
<code>input</code>	Input for the next command. Can be a string, or an array.
<code>maxlocktime</code>	<code>MaxLockTime</code> used for all following commands.
<code>maxresults</code>	<code>MaxResults</code> used for all following commands.
<code>maxscanrows</code>	<code>MaxScanRows</code> used for all following commands.
<code>p4config_file</code>	The location of the configuration file used (<code>P4CONFIG</code>). This property is read-only.
<code>password</code>	<code>P4PASSWD</code> , the password used.
<code>port</code>	<code>P4PORT</code> , the port used for the connection
<code>prog</code>	The name of the script.
<code>server_level</code>	Returns the current Perforce server level. This property is read only.
<code>streams</code>	Enable or disable support for streams.
<code>tagged</code>	To disable tagged output for the following commands, set the value to 0 or False. By default, tagged output is enabled.
<code>ticket_file</code>	<code>P4TICKETS</code> , the ticket file location used.
<code>user</code>	<code>P4USER</code> , the user under which the connection is run.

Property	Description
<code>version</code>	The version of the script.
<code>warnings</code>	A read-only array containing the warning messages received during execution of the last command.

The following table lists all public methods of the class **P4**.

Method	Description
<code>connect()</code>	Connects to the Perforce server.
<code>connected()</code>	Returns True if connected and the connection is alive, otherwise False .
<code>delete_<spectype>()</code>	Deletes the spec <spectype>. Equivalent to the command: <pre>P4::run("<spectype>", "-d");</pre>
<code>disconnect()</code>	Disconnects from the Perforce server.
<code>env()</code>	Get the value of a Perforce environment variable, taking into account P4CONFIG files and (on Windows or OS X) the registry or user preferences.
<code>identify()</code>	Returns a string identifying the P4PHP module. (This method is static.)
<code>fetch_<spectype>()</code>	Fetches the spec <spectype>. Equivalent to the command: <pre>P4::run("<spectype>", "-o");</pre>
<code>format_<spectype>()</code>	Converts the spec <spectype> into a string.
<code>parse_<spectype>()</code>	Parses a string representation of the spec <spectype> and returns an array.
<code>run()</code>	Runs a command on the server. Needs to be connected, or an exception is raised.
<code>run_cmd()</code>	Runs the command <i>cmd</i> . Equivalent to: <pre>P4::run("cmd");</pre>
<code>run_filelog()</code>	This command returns an array of P4_DepotFile objects. Specialization for the <code>run()</code> command.
<code>run_login()</code>	Logs in using the specified password or ticket.

Method	Description
run_password()	Convenience method: updates the password. Takes two arguments: <i>oldpassword</i> , <i>newpassword</i> .
run_resolve()	Interface to <code>p4 resolve</code> .
run_submit()	Convenience method for submitting changelists. When invoked with a change spec, it submits the spec. Equivalent to: <pre>p4::input = myspec; p4::run("submit", "-i");</pre>
save_<spectype>()	Saves the spec < <i>spectype</i> >. Equivalent to the command: <pre>P4::run("<spectype>", "-i");</pre>

P4_Exception

Exception class. Instances of this class are raised when errors and/or (depending on the `exception_level` setting) warnings are returned by the server. The exception contains the errors in the form of a string. `P4_Exception` extends the standard PHP `Exception` class.

P4_DepotFile

Container class returned by `P4::run_filelog()`. Contains the name of the depot file and an array of `P4_Revision` objects.

Property	Description
depotFile	Name of the depot file
revisions	Array of Revision objects.

P4_Revision

Container class containing one revision of a `P4_DepotFile` object.

Property	Description
action	Action that created the revision.
change	Changelist number.
client	Client workspace used to create this revision.

Property	Description
<code>desc</code>	Short changelist description.
<code>depotFile</code>	The name of the file in the depot.
<code>digest</code>	MD5 digest of the revision.
<code>fileSize</code>	File size of this revision.
<code>integrations</code>	Array of <code>P4_Integration</code> objects.
<code>rev</code>	Revision.
<code>time</code>	Timestamp.
<code>type</code>	File type.
<code>user</code>	User that created this revision.

P4_Integration

Container class containing one integration for a `P4_Revision` object.

Property	Description
<code>how</code>	Integration method (merge/branch/copy/ignored).
<code>file</code>	Integrated file.
<code>srev</code>	Start revision.
<code>erev</code>	End revision.

P4_Map

A class that allows users to create and work with Perforce mappings without requiring a connection to the Perforce server.

Method	Description
<code>__construct()</code>	Construct a new Map object.
<code>join()</code>	Joins two maps to create a third (static method).
<code>clear()</code>	Empties a map.
<code>count()</code>	Returns the number of entries in a map.
<code>is_empty()</code>	Tests whether or not a map object is empty.

Method	Description
insert()	Inserts an entry into the map.
translate()	Translate a string through a map.
includes()	Tests whether a path is mapped.
reverse()	Returns a new mapping with the left and right sides reversed.
lhs()	Returns the left side as an array.
rhs()	Returns the right side as an array.
as_array()	Returns the map as an array.

P4_MergeData

Class encapsulating the context of an individual merge during execution of a `p4 resolve` command. Passed to `P4::run_resolve()`.

Property	Description
your_name	Returns the name of "your" file in the merge. (file in workspace)
their_name	Returns the name of "their" file in the merge. (file in the depot)
base_name	Returns the name of "base" file in the merge. (file in the depot)
your_path	Returns the path of "your" file in the merge. (file in workspace)
their_path	Returns the path of "their" file in the merge. (temporary file on workstation into which <code>their_name</code> has been loaded)
base_path	Returns the path of the base file in the merge. (temporary file on workstation into which <code>base_name</code> has been loaded)
result_path	Returns the path to the merge result. (temporary file on workstation into which the automatic merge performed by the server has been loaded.)
merge_hint	Returns hint from server as to how user might best resolve merge.

P4_OutputHandlerAbstract

Handler class that provides access to streaming output from the server; set `$p4->handler` to an instance of a subclass of `P4_OutputHandlerAbstract` to enable callbacks:

Method	Description
outputBinary()	Process binary data.

Method	Description
outputInfo()	Process tabular data.
outputMessage()	Process information or errors.
outputStat()	Process tagged output.
outputText()	Process text data.

P4_Resolver

Abstract class for handling resolves in Perforce. This class must be subclassed in order to be used.

Method	Description
resolve()	Perform a resolve and return the resolve decision as a string.

Class P4

Description

Main interface to the PHP client API.

This module provides an object-oriented interface to the Perforce version management system. Data is returned in arrays and input can also be supplied in these formats.

Each **P4** object represents a connection to the Perforce server, and multiple commands may be executed (serially) over a single connection (which of itself can result in substantially improved performance if executing long sequences of Perforce commands).

1. Instantiate your **P4** object.
2. Specify your Perforce client environment:
 - **client**
 - **host**
 - **password**
 - **port**
 - **user**
3. Set any options to control output or error handling:
 - **exception_level**
4. Connect to the Perforce service.

The Perforce protocol is not designed to support multiple concurrent queries over the same connection. Multithreaded applications that use the C++ API or derived APIs (including P4PHP) should ensure that a separate connection is used for each thread, or that only one thread may use a shared connection at a time.

5. Run your Perforce commands.
6. Disconnect from the Perforce service.

Properties

P4::api_level -> int

Contains the API compatibility level desired. This is useful when writing scripts using Perforce commands that do not yet support tagged output. In these cases, upgrading to a later server that supports tagged output for the commands in question can break your script. Using this method allows you to lock your script to the output format of an older Perforce release and facilitate seamless upgrades. Must be called before calling **P4::connect()**.

```
<?php

$p4 = new P4();
$p4->api_level = 57; // Lock to 2005.1 format
$p4->connect();

...

$p4->disconnect();

?>
```

For the API integer levels that correspond to each Perforce release, see:

<http://kb.perforce.com/article/512>

P4::charset -> string

Contains the character set to use when connect to a Unicode enabled server. Do not use when working with non-Unicode-enabled servers. By default, the character set is the value of the **P4CHARSET** environment variable. If the character set is invalid, this method raises a **P4_Exception**.

```
<?php

$p4 = new P4();
$p4->client = "www";
$p4->charset = "iso8859-1";

$p4->connect();
$p4->run_sync();
$p4->disconnect();

?>
```

P4::client -> string

Contains the name of your client workspace. By default, this is the value of the **P4CLIENT** taken from any **P4CONFIG** file present, or from the environment according to the normal Perforce conventions.

P4::cwd -> string

Contains the current working directory. Can be called prior to executing any Perforce command. Sometimes necessary if your script executes a **chdir()** as part of its processing.

```
<?php

$p4 = new P4();
$p4->cwd = "/home/bruno"

?>
```

P4::errors -> array (read-only)

Returns an array containing the error messages received during execution of the last command.

```
<?php

$p4 = new P4();
$p4->connect();
$p4->exception_level = 1;
$p4->connect(); // P4_Exception on failure
$p4->run_sync(); // File(s) up-to-date is a warning; no exception raised

$error = $p4->errors;
print_r( $error );

$p4->disconnect();

?>
```

P4::exception_level -> int

Configures the events which give rise to exceptions. The following three levels are supported:

- **0** : disables all exception handling and makes the interface completely procedural; you are responsible for checking the **P4::errors** and **P4::warnings** arrays.
- **1** : causes exceptions to be raised only when errors are encountered.
- **2** : causes exceptions to be raised for both errors and warnings. This is the default.

For example:

```
<?php

$p4 = new P4();
$p4->exception_level = 1;
$p4->connect(); // P4_Exception on failure
$p4->run_sync(); // File(s) up-to-date is a warning; no exception raised
$p4->disconnect();

?>
```

P4::expand_sequences -> bool

Controls whether keys with trailing numbers are expanded into arrays when using tagged output. By default, **expand_sequences** is **true** to maintain backwards compatibility. Expansion can be enabled and disabled on a per-command basis.

For example:

```
<?php

$p4 = new P4();
$p4->connect();
$p4->expand_sequences = false; // disables sequence expansion.
$result = $p4->run( 'fstat', '-0a', '//depot/path/...' );
var_dump( $result );

?>
```

P4::handler -> handler

Contains the output handler.

P4::host -> string

Contains the name of the current host. It defaults to the value of **P4HOST** taken from any **P4CONFIG** file present, or from the environment as per the usual Perforce convention. Must be called before connecting to the Perforce server.

```
<?php

$p4 = new P4();
$p4->host = "workstation123.perforce.com";
$p4->connect();

?>
```

P4::input -> string | array

Contains input for the next command.

Set this property prior to running a command that requires input from the user. When the command requests input, the specified data is supplied to the command. Typically, commands of the form **p4 cmd -i** are invoked using the **P4::save_<spectype>()** methods, which retrieve the value from **P4::input** internally; there is no need to set **P4::input** when using the **P4::save_<spectype>()** shortcuts.

You may pass a string, an array, or (for commands that take multiple inputs from the user) an array of strings or arrays. If you pass an array, note that the first element of the array will be popped each time Perforce asks the user for input.

For example, the following code supplies a description for the default changelist and then submits it to the depot:

```
<?php

$p4 = new P4();
$p4->connect();

$change = $p4->run_change( "-o" )[0];
$change[ 'Description' ] = "Autosubmitted changelist";
$p4->input = $change;
$p4->run_submit( "-i" );
$p4->disconnect();

?>
```

P4::maxlocktime -> int

Limit the amount of time (in milliseconds) spent during data scans to prevent the server from locking tables for too long. Commands that take longer than the limit will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxlocktime` for information on the commands that support this limit.

P4::maxresults -> int

Limit the number of results Perforce permits for subsequent commands. Commands that produce more than this number of results will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxresults` for information on the commands that support this limit.

P4::maxscanrows -> int

Limit the number of database records Perforce scans for subsequent commands. Commands that attempt to scan more than this number of records will be aborted. The limit remains in force until you disable it by setting it to zero. See `p4 help maxscanrows` for information on the commands that support this limit.

P4::p4config_file -> string (read-only)

Contains the name of the current `P4CONFIG` file, if any. This property cannot be set.

P4::password -> string

Contains your Perforce password or login ticket. If not used, takes the value of `P4PASSWD` from any `P4CONFIG` file in effect, or from the environment according to the normal Perforce conventions.

This password is also used if you later call `P4::run_login()` to log in using the 2003.2 and later ticket system. After running `P4::run_login()`, the property contains the ticket allocated by the server.

```
<?php

$p4 = new P4();
$p4->password = "mypass";
$p4->connect();
$p4->run_login();

...

$p4->disconnect();

?>
```

P4::port -> string

Contains the host and port of the Perforce server to which you want to connect. It defaults to the value of **P4PORT** in any **P4CONFIG** file in effect, and then to the value of **P4PORT** taken from the environment.

```
<?php

$p4 = new P4();
$p4->port = "localhost:1666";
$p4->connect();

...

$p4->disconnect();

?>
```

P4::prog -> string

Contains the name of the program, as reported to Perforce system administrators running **p4 monitor show -e**. The default is **unnamed p4-php script**

```
<?php

$p4 = new P4();
$p4->prog = "sync-script";
print $p4->prog;
$p4->connect();

...

$p4->disconnect();

?>
```

P4::server_level -> int (read-only)

Returns the current Perforce server level. Each iteration of the Perforce server is given a level number. As part of the initial communication this value is passed between the client application and the Perforce server. This value is used to determine the communication that the Perforce server will understand. All subsequent requests can therefore be tailored to meet the requirements of this server level.

This property is 0 before the first command is run, and is set automatically after the first communication with the server.

For the API integer levels that correspond to each Perforce release, see:

<http://kb.perforce.com/article/571>

P4::streams -> bool

If **true**, **P4::streams** enables support for streams. By default, streams support is enabled at 2011.1 or higher (**api_level** >= 70). Raises a **P4Exception** if you attempt to enable streams on a pre-2011.1 server. You can enable or disable support for streams both before and after connecting to the server.

```
<?php

```

P4::tagged -> bool

If **true**, **P4::tagged** enables tagged output. By default, tagged output is on.

```
<?php

```

P4::ticket_file -> string

Contains the location of the **P4TICKETS** file.

P4::user -> string

Contains the Perforce username. It defaults to the value of **P4USER** taken from any **P4CONFIG** file present, or from the environment as per the usual Perforce convention.

```
<?php

$p4 = new P4();
$p4->user = "bruno";
$p4->connect();
...
P4::disconnect();

?>
```

P4::version -> string

Contains the version of the program, as reported to Perforce system administrators in the server log.

```
<?php

$p4 = new P4();
$p4->version = "123";
print $p4->version;
$p4->connect();
...
$p4->disconnect();

?>
```

P4::warnings -> array (read-only)

Contains the array of warnings that arose during execution of the last command.

```
<?php

$p4 = new P4();
$p4->connect(); // P4_Exception on failure
$p4->exception_level = 2;

$files = $p4->run_sync();
$warn = $p4->warnings;
print_r( $warn );

$p4->disconnect();

?>
```

Constructor

P4::__construct

Construct a new **P4** object. For example:

```
<?php
$p4 = new P4();
?>
```

Static Methods

P4::identify() -> string

Return the version of P4PHP that you are using, and, if applicable, the version of the OpenSSL library used for building the underlying Perforce C++ API with which P4PHP was built).

```
<?php
print P4::identify();
?>
```

produces output similar to the following:

```
Perforce - The Fast Software Configuration Management System.
Copyright 1995-2013 Perforce Software. All rights reserved.
Rev. P4PHP/LINUX26X86/2013.1/644389 (2013.1 API) (2013/05/21).
```

Instance Methods

P4::connect() -> bool

Initializes the Perforce client and connects to the server.

If the connection is successfully established, returns **None**. If the connection fails and **exception_level** is 0, returns False, otherwise raises a **P4_Exception**. If already connected, prints a message.

```
<?php
$p4 = new P4();
$p4->connect();
...
$p4->disconnect();
?>
```

P4::connected() -> bool

Returns **true** if connected to the Perforce server and the connection is alive, otherwise **false**.

```
<?php

$p4 = new P4();
if ( !$p4->connected() ) {
    print "Not Connected\n";
}

$p4->connect();
if ( $p4->connected() ) {
    print "Connected\n";
}

$p4->disconnect();

?>
```

P4::delete_<spectype>([options], name) -> array

The `delete_<spectype>()` methods are shortcut methods that allow you to delete the definitions of clients, labels, branches, etc. These methods are equivalent to:

```
P4::run( "<spectype>", '-d', [options], "spec name" );
```

The following code uses `P4::delete_client()` to delete client workspaces that have not been accessed in more than 365 days:

```
<?php

$p4 = new P4();
try {
    $p4->connect();
    foreach ( $p4->run_clients() as $client ) {
        $atime = int( $client['Access'] );
        // If the client has not been accessed for a year, delete it
        if ( (time() - $atime) > 31536000 ) { // seconds in 365 days
            $p4->delete_client( "-f", $client["Client"] );
        }
    }
} catch ( P4_Exception $e ) {
    print $e->getMessage() . "\n";
    foreach ( $p4->errors as $error ) {
        print "Error: $error\n";
    }
}
?>
```

P4::disconnect() -> void

Disconnect from the Perforce server. Call this method before exiting your script.

```
<?php

$p4 = new P4();
$p4->connect();
...
$p4->disconnect();

?>
```

P4::env(var) -> string

Get the value of a Perforce environment variable, taking into account **P4CONFIG** files and (on Windows or OS X) the registry or user preferences.

```
<?php

$p4 = new P4();
print $p4->env( "P4PORT" );

?>
```

P4::fetch_<spectype>() -> array

The `fetch_<spectype>()` methods are shortcuts for running `$p4->run( "<spectype>", "-o" )` and returning the first element of the array. For example:

```
$label      = $p4->fetch_label( "labelname" );
$change     = $p4->fetch_change( $change );
$clientspec = $p4->fetch_client( "clientname" );
```

are equivalent to:

```
$label      = $p4->run( "label", "-o", "labelname" );
$change     = $p4->run( "change", "-o", $change );
$clientspec = $p4->run( "client", "-o", $clientname );
```

P4::format_spec("<spectype>", array) -> string

Converts the fields in the array containing the elements of a Perforce form (spec) into the string representation familiar to users. The first argument is the type of spec to format: for example, client, branch, label, and so on. The second argument is the hash to parse.

There are shortcuts available for this method. You can use `$p4->format_<spectype>( array )` instead of `$p4->format_spec( "<spectype>", array )`, where `<spectype>` is the name of a Perforce spec, such as client, label, etc.

P4::format_<spectype>(array) -> string

The `format_<spectype>()` methods are shortcut methods that allow you to quickly fetch the definitions of clients, labels, branches, etc. They're equivalent to:

```
$p4->format_spec( "<spectype>", array );
```

P4::parse_spec("<spectype>", string) -> array

Parses a Perforce form (spec) in text form into an array using the spec definition obtained from the server. The first argument is the type of spec to parse: `client`, `branch`, `label`, and so on. The second argument is the string buffer to parse.

There are shortcuts available for this method. You can use:

```
$p4->parse_<spectype>( buf );
```

instead of:

```
$p4->parse_spec( "<spectype>", buf );
```

where `<spectype>` is one of `client`, `branch`, `label`, and so on.

P4::parse_<spectype>(string) -> array

This is equivalent to:

```
$p4->parse_spec( "<spectype>", string )
```

For example:

```
$p4->parse_job( myJob );
```

converts the String representation of a job spec into an array.

To parse a spec, P4 needs to have the spec available. When not connected to the Perforce server, P4 assumes the default format for the spec, which is hardcoded. This assumption can fail for jobs if the server's jobspec has been modified. In this case, your script can load a job from the server first with the command `fetch_job( "somename"`), and P4 will cache and use the spec format in subsequent `P4::parse_job()` calls.

P4::run(<cmd>, [arg, ...]) -> mixed

Base interface to all the run methods in this API. Runs the specified Perforce command with the arguments supplied. Arguments may be in any form as long as they can be converted to strings.

The `P4::run()` method returns an array of results whether the command succeeds or fails; the array may, however, be empty. Whether the elements of the array are strings or arrays depends on:

- i. server support for tagged output for the command, and
- ii. whether tagged output was disabled by calling `$p4->tagged = false`.

In the event of errors or warnings, and depending on the exception level in force at the time, `P4::run()` raises a `P4_Exception`. If the current exception level is below the threshold for the error/warning, `P4::run()` returns the output as normal and the caller must explicitly review `P4::errors` and `P4::warnings` to check for errors or warnings.

```
<?php

```

Shortcuts are available for `P4::run`. For example:

```
$p4->run_command( "args");
```

is equivalent to:

```
$p4->run( "command", args );
```

There are also some shortcuts for common commands such as editing Perforce forms and submitting. For example, this:

```
<?php

```

may be shortened to:

```
<?php

$p4 = new P4();
$p4->connect();

$clientspec = $p4->fetch_spec();
$clientspec["Description"] = "Build client";

$p4->save_client( $clientspec );

$p4->disconnect();

?>
```

The following are equivalent:

Shortcut	Equivalent to
<code>\$p4->delete_<spectype>();</code>	<code>\$p4->run("<spectype>", "-d ");</code>
<code>\$p4->fetch_<spectype>();</code>	<code>array_shift(\$p4->run("<spectype>", "-o "));</code>
<code>\$p4->save_<spectype>(spec);</code>	<code>\$p4->input = \$spec;</code> <code>\$p4->run("<spectype>", "-i");</code>

As the commands associated with `P4::fetch_<spectype>()` typically return only one item, these methods do not return an array, but instead return the first result element.

For convenience in submitting changelists, changes returned by `P4::fetch_change()` can be passed to `P4::run_submit()`. For example:

```
<?php

$p4 = new P4();
$p4->connect();

$spec = $p4->fetch_change();
$spec["Description"] = "Automated change";
$p4->run_submit( $spec );

$p4->disconnect();

?>
```

P4::run_<cmd>() -> mixed

Shorthand for:

```
P4::run( "cmd", arguments... );
```

P4::run_filelog(<fileSpec>) -> array

Runs a `p4 filelog` on the *fileSpec* provided and returns an array of `P4_DepotFile` results (when executed in tagged mode), or an array of strings when executed in nontagged mode. By default, the raw output of `p4 filelog` is tagged; this method restructures the output into a more user-friendly (and object-oriented) form.

For example:

```
<?php
$p4 = new P4();
try {
    $p4->connect();
    $filelog = $p4->run_filelog( "index.html" );
    foreach ( $filelog->revisions as $revision ) {
        // do something
    }
} catch ( P4_Exception $e ) {
    print $e->getMessage() . "\n";
    foreach ( $p4->errors as $error ) {
        print "Error: $error\n";
    }
}
?>
```

P4::run_login(arg...) -> array

Runs `p4 login` using a password or ticket set by the user.

P4::run_password(oldpass, newpass) -> array

A thin wrapper to make it easy to change your password. This method is equivalent to the following:

```
<?php
$p4->input = array( $oldpass, $newpass, $newpass );
$p4->run( "password" );

?>
```

For example:

```
<?php

$p4 = new P4();
$p4->password = "myoldpass";

try {
    $p4->connect();
    $p4->run_password( "myoldpass", "mynewpass" );
    $p4->disconnect();
} catch ( P4_Exception $e ) {
    print $e->getMessage() . "\n";
    foreach ( $p4->errors as $error ) {
        print "Error: $error\n";
    }
}
?>
```

P4::run_resolve([<resolver>], [arg...]) -> array

Run a `p4 resolve` command. Interactive resolves require the *<resolver>* parameter to be an object of a class derived from `P4_Resolver`. In these cases, the `P4::Resolver::resolve()` method is called to handle the resolve. For example:

```
<?php

$p4->run_resolve( new MyResolver() );

?>
```

To perform an automated merge that skips whenever conflicts are detected:

```
<?php

class MyResolver extends P4_Resolver {
    public function resolve( $merge_data ) {
        if ( $merge_data->merge_hint != 'e' ) {
            return $merge_data->merge_hint;
        } else {
            return "s"; // skip, there's a conflict
        }
    }
}

?>
```

In non-interactive resolves, no `P4_Resolver` object is required. For example:

```
$p4->run_resolve ( "-at" );
```

P4::run_submit([array], [arg...]) -> array

Submit a changelist to the server. To submit a changelist, set the fields of the changelist as required and supply any flags:

```
$p4->change = $p4->fetch_change();
$change["Description"] = "Some description";
$p4->run_submit( "-r", $change );
```

You can also submit a changelist by supplying the arguments as you would on the command line:

```
$p4->run_submit( "-d", "Some description", "somedir/..." );
```

P4::save_<spectype>()

The `save_<spectype>()` methods are shortcut methods that allow you to quickly update the definitions of clients, labels, branches, etc. They are equivalent to:

```
$p4->input = $arrayOrString;
$p4->run( "<spectype> ", "-i" );
```

For example:

```
<?php
$p4 = new P4();
try {
    $p4->connect();
    $client = $p4->fetch_client();
    $client["Owner"] = $p4->user;
    $p4->save_client( $client );
    $p4->disconnect();
} catch ( P4_Exception $e ) {
    print $e->getMessage() . "\n";
    foreach ( $p4->errors as $error ) {
        print "Error: $error\n";
    }
}
?>
```

Class P4_Exception

Description

Instances of this class are raised when **P4** encounters an error or a warning from the server. The exception contains the errors in the form of a string. **P4_Exception** is an extension of the standard Exception class.

Class Attributes

None.

Static Methods

None.

Class P4_DepotFile

Description

Utility class providing easy access to the attributes of a file in a Perforce depot. Each **P4_DepotFile** object contains summary information about the file and an array of revisions (**P4_Revision** objects) of that file. Currently, only the **P4::run_filelog()** method returns an array of **P4_DepotFile** objects.

Properties

\$df->depotFile -> string

Returns the name of the depot file to which this object refers.

\$df->revisions -> array

Returns an array of **P4_Revision** objects, one for each revision of the depot file.

Static Methods

None.

Instance Methods

None.

Class P4_Revision

Description

Utility class providing easy access to the revisions of `P4_DepotFile` objects. Created by `P4::run_filelog()`.

Properties

`$rev->action -> string`

Returns the name of the action which gave rise to this revision of the file.

`$rev->change -> long`

Returns the change number that gave rise to this revision of the file.

`$rev->client -> string`

Returns the name of the client from which this revision was submitted.

`$rev->depotFile -> string`

Returns the name of the depot file to which this object refers.

`$rev->desc -> string`

Returns the description of the change which created this revision. Note that only the first 31 characters are returned unless you use `p4 filelog -l` for the first 250 characters, or `p4 filelog -l` for the full text.

`$rev->digest -> string`

Returns the MD5 digest of this revision.

`$rev->fileSize -> long`

Returns this revision's size in bytes.

`$rev->integrations -> array`

Returns the array of `P4_Integration` objects for this revision.

`$rev->rev -> long`

Returns the number of this revision of the file.

`$rev->time -> string`

Returns the date / time that this revision was created.

`$rev->type -> string`

Returns this revision's Perforce filetype.

`$rev->user -> string`

Returns the name of the user who created this revision.

Static Methods

None.

Instance Methods

None.

Class P4_Integration

Description

Utility class providing easy access to the details of an integration record. Created by `P4::run_filelog()`.

Properties

`$integ->how -> string`

Returns the type of the integration record - how that record was created.

`$integ->file -> string`

Returns the path to the file being integrated to/from.

`$integ->srev -> int`

Returns the start revision number used for this integration.

`$integ->erev -> int`

Returns the end revision number used for this integration.

Static Methods

None.

Instance Methods

None.

Class P4_Map

Description

The **P4_Map** class allows users to create and work with Perforce mappings, without requiring a connection to a Perforce server.

Properties

None.

Constructor

P4_Map::__construct([array]) -> P4_Map

Constructs a new **P4_Map** object.

Static Methods

P4_Map::join (map1, map2) -> P4_Map

Join two **P4_Map** objects and create a third **P4_Map**. The new map is composed of the left-hand side of the first mapping, as joined to the right-hand side of the second mapping. For example:

```
// Map depot syntax to client syntax
$client_map = new P4_Map();
$client_map->insert( "//depot/main/...", "//client/..." );

// Map client syntax to local syntax
$client_root = new P4_Map();
$client_root->insert( "//client/...", "/home/bruno/workspace/..." );

// Join the previous mappings to map depot syntax to local syntax
$local_map = P4_Map::join( $client_map, $client_root );
$local_path = $local_map->translate( "//depot/main/www/index.html" );

// local_path is now /home/bruno/workspace/www/index.html
```

Instance Methods

\$map->clear() -> void

Empty a map.

\$map->count() -> int

Return the number of entries in a map.

`$map->is_empty() -> bool`

Test whether a map object is empty.

`$map->insert( string ... ) -> void`

Inserts an entry into the map.

May be called with one or two arguments. If called with one argument, the string is assumed to be a string containing either a half-map, or a string containing both halves of the mapping. In this form, mappings with embedded spaces must be quoted. If called with two arguments, each argument is assumed to be half of the mapping, and quotes are optional.

```
// called with two arguments:
$map->insert( "//depot/main/...", "//client/..." );

// called with one argument containing both halves of the mapping:
$map->insert( "//depot/live/... //client/live/..." );

// called with one argument containing a half-map:
// This call produces the mapping "depot/... depot/..."
$map->insert( "depot/..." );
```

`$map->translate ( string, [ bool ] )-> string`

Translate a string through a map, and return the result. If the optional second argument is **1**, translate forward, and if it is **0**, translate in the reverse direction. By default, translation is in the forward direction.

`$map->includes( string ) -> bool`

Tests whether a path is mapped or not.

```
if $map->includes( "//depot/main/..." ) {
    ...
}
```

`$map->reverse() -> P4_Map`

Return a new **P4_Map** object with the left and right sides of the mapping swapped. The original object is unchanged.

`$map->lhs() -> array`

Returns the left side of a mapping as an array.

`$map->rhs() -> array`

Returns the right side of a mapping as an array.

`$map->as_array() -> array`

Returns the map as an array.

Class P4_MergeData

Description

Class containing the context for an individual merge during execution of a `p4 resolve`.

Properties

`$md->your_name -> string`

Returns the name of "your" file in the merge. This is typically a path to a file in the workspace.

`$md->their_name -> string`

Returns the name of "their" file in the merge. This is typically a path to a file in the depot.

`$md->base_name -> string`

Returns the name of the "base" file in the merge. This is typically a path to a file in the depot.

`$md->your_path -> string`

Returns the path of "your" file in the merge. This is typically a path to a file in the workspace.

`$md->their_path -> string`

Returns the path of "their" file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `their_name` have been loaded.

`$md->base_path -> string`

Returns the path of the base file in the merge. This is typically a path to a temporary file on your local machine in which the contents of `base_name` have been loaded.

`$md->result_path -> string`

Returns the path to the merge result. This is typically a path to a temporary file on your local machine in which the contents of the automatic merge performed by the server have been loaded.

`$md->merge_hint -> string`

Returns the hint from the server as to how it thinks you might best resolve this merge.

Class P4_OutputHandlerAbstract

Description

The `P4_OutputHandlerAbstract` class is a handler class that provides access to streaming output from the server. After defining the output handler, set `$p4->handler` to an instance of a subclass of `P4_OutputHandlerAbstract`.

By default, `P4_OutputHandlerAbstract` returns `HANDLER_REPORT` for all output methods. The different return options are:

Value	Meaning
<code>HANDLER_REPORT</code>	Messages added to output (don't handle, don't cancel).
<code>HANDLER_HANDLED</code>	Output is handled by class (don't add message to output).
<code>HANDLER_CANCEL</code>	Operation is marked for cancel, message is added to output.

Class Methods

class MyHandler extends P4_OutputHandlerAbstract

Constructs a new subclass of `P4_OutputHandlerAbstract`.

Instance Methods

`$handler->outputBinary -> int`

Process binary data.

`$handler->outputInfo -> int`

Process tabular data.

`$handler->outputMessage -> int`

Process informational or error messages.

`$handler->outputStat -> int`

Process tagged data.

`$handler->outputText -> int`

Process text data.

Class P4_Resolver

Description

P4_Resolver is a class for handling resolves in Perforce. It must be subclassed, to be used; subclasses can override the **P4::resolve()** method. When **P4::run_resolve()** is called with a **P4_Resolver** object, it calls the **P4_Resolver::resolve()** method of the object once for each scheduled resolve.

Properties

None.

Static Methods

None.

Instance Methods

\$resolver->resolve(self, mergeData) -> string

Returns the resolve decision as a string. The standard Perforce resolve strings apply:

String	Meaning
ay	Accept Yours.
at	Accept Theirs.
am	Accept Merge result.
ae	Accept Edited result.
s	Skip this merge.
q	Abort the merge.

By default, all automatic merges are accepted, and all merges with conflicts are skipped. The **P4_Resolver::resolve()** method is called with a single parameter, which is a reference to a **P4_MergeData** object.

Perforce software includes software developed by the University of California, Berkeley and its contributors. This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

